



EUROPEAN COMMISSION

DIGIT
Connecting Europe Facility

Domibus

Interface Control Document

Default JMS Plugin

Version [1.07]

Status [Final]

Date: 9/10/2017

Document Approver(s):

Approver Name	Role
Joao RODRIGUES	Program Manager

Document Reviewers:

Reviewer Name	Role
Joao RODRIGUES	Program Manager
Adrien FERAL	Product Owner
Daniels MAARTEN	Tester
Ioana DRAGUSANU	Developer
Yves ADAM	Quality Manager
Christian Koch	eCodex team
Cosmin BACIU	Developer
Tiago MIGUEL	Developer
Caroline AEBY and Chaouki BERRAH	Technical Writers

Summary of Changes:

Version	Date	Created by	Short Description of Changes
0.01	18/03/2016	Pedro TAVARES	Initial version
0.02	31/03/2016	Pedro TAVARES	Update with comments of eCodex Update section 4.1 with simple function for submitting a message
0.03	06/04/2016	Pedro TAVARES	Update section 4.1 with simple function for submitting a message
1.00	15/05/2016	Pedro TAVARES	Update document with the new format
1.01	08/08/2016	Pedro TAVARES	Update document with Yves ADAM comments
1.02	31/08/2016	Yves ADAM	Upgrade from version 3.1.1 to 3.2
1.03	22/03/2017	Cosmin BACIU	Upgrade from version 3.2 to 3.2.3
1.04	10/04/2017	Cosmin BACIU	Use a Domibus generic version instead of a specific version
1.05	29/06/2017	Cosmin BACIU	Updated the JMS properties to use _ instead of -
1.06	07/09/2017	Tiago MIGUEL	Updated the JMS plugin properties to expose in the OUT queue the message payload's file location. Reviewed document contents and formatting
1.7	09/10/2017	CEF Support	List of reviewers updated.

Table of Contents

1. INTRODUCTION	4
1.1. Purpose.....	4
1.2. Scope	4
1.3. Audience.....	5
1.4. References.....	5
1.5. Acronyms.....	7
2. INTERFACE FUNCTIONAL SPECIFICATION	8
2.1. The four corner model	8
2.2. Introduction to Domibus - AS4.....	9
3. INTERFACE BEHAVIOURAL SPECIFICATION.....	10
3.1. JMS-Messages	12
3.2. JMS-Queues.....	14
3.2.1. domibus.backend.jmsInQueue.....	14
3.2.2. domibus.backend.jms.replyQueue	15
3.2.3. domibus.backend.jms.outQueue	16
3.2.4. domibus.backend.jms.errorNotifyProducer	17
3.2.5. domibus.backend.jms.errorNotifyConsumer.....	18
4. ANNEXE 1 – INTERFACE POLICY SPECIFICATION	19
5. ANNEX 2 - ERRORS CODES TABLE	20
6. ANNEXE 3 – DOCUMENT PARTS	23
7. LIST OF FIGURES	24
8. LIST OF TABLES	24
9. CONTACT INFORMATION	25

1. INTRODUCTION

1.1. Purpose

The purpose of this document is to outline the JMS Data Format Exchange to be used as part of the default JMS backend integration solution for the Domibus Access Point¹.

According to CEF eDelivery, an Access Point is an implementation of the OpenPEPPOL AS2 Profile or the e-SENS AS4 Profile. The data exchange protocols of CEF eDelivery are profiles, meaning that several options of the original technical specifications were narrowed down in order to increase consistency, interoperability and to simplify deployment. The profile of AS2 was developed by OpenPEPPOL², and the profile of AS4 was developed by e-SENS³ in collaboration with several service providers while being implemented in the e-Justice domain by e-CODEX. An Access Point exposes two interfaces:

- An interface to connect the Backend system with the Access Point. Typically, this interface is customisable as communication between Access Points and Backend systems may use any messaging or transport protocol.
- A standard messaging interface between Access Points, this interface is configurable according to the options of the profiles supported by CEF eDelivery. It is important to note that CEF eDelivery standardises the communication only between the Access Points.

This document will univocally define the JMS plugin that acts as an interface to the Access Point (Corner Two and Corner Three in the four corner topology that will be explained later in this document) component of the CEF eDelivery building block.

There is 1 interface described in this document:

Interface	Description	Version
JMS backend integration	The JMS plugin	3.x.y

Table 1 - Interface escribed

1.2. Scope

This document covers the service interface of the Access Point from the perspective of the JMS backend integration. It includes information regarding the description of the JMS-Queues, information model and the types of messages for the services provided. This specification addresses no more than the service interface of the Access Point. All other aspects of its implementation are not covered by this document (i.e. the service consumer). The ICD specification provides both the provider (i.e. the implementer) of the services and their consumers with a complete specification of the following aspects:

¹ <https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus+++v3.3>

² http://www.peppol.eu/about_peppol/about-openpeppol-1

³ <http://www.eSENS.eu/content/about-project>

- Interface Functional Specification, this specifies the set of services and the operations provided by each service;
- Interface Behavioural Specification, this specifies the expected sequence of steps to be respected when calling a service or a set of services;
- Interface Message standards, this specifies the syntax and semantics of the data and metadata;
- Interface Policy Specification, this specifies constraints and policies regarding the operation of the service.

1.3. Audience

This document is intended to:

- The Directorate Generals and Services of the European Commission, Member States (MS) and also companies of the private sector wanting to set up a connection between their backend systems and the Access Point. In particular:
- Architects will find it useful for determining how to best exploit the Access Point to create a fully-fledged solution and as a starting point for connecting a Back-Office system to the Access Point.
- Analysts will find it useful to understand the Access Point that will enable them to have a holistic and detailed view of the operations and data involved in the use cases.
- Developers will find it essential as a basis of their development concerning the Access Point plugin services.
- Testers can use this document in order to test the interface by following the use cases described.

1.4. References

The table below provides the reader with the list of reference documents.

#	Document	Contents outline
[REF1]	Introduction to the Connecting Europe Facility - eDelivery building block	Overview of eDelivery
[REF2]	Using HTTP Methods for RESTful Services	Short description of HTTP Methods for RESTful Services
[REF3]	Business Document Metadata Service Location - Software Architecture Document	This document is the Software Architecture document of the CIPA eDelivery Business Document Metadata Service Location application (BDMSL) sample implementation. It intends to provide detailed information about the project: 1) An overview of the solution 2) The different layers 3) The principles governing its software architecture.
[REF4]	ebXML (Electronic Business using eXtensible Markup Language)	ebXML (Electronic Business using eXtensible Markup Language)
[REF5]	Web Services Description Language (WSDL) 1.1	Web Services Description Language (WSDL) 1.1 WS-I Basic Profile Version 1.1
[REF6]	XML Schema 1.1	XML Schema 1.1

[REF7]	Extensible Markup Language (XML) 1.0	Extensible Markup Language (XML) 1.0
[REF8]	Hypertext Transfer Protocol 1.1	Hypertext Transfer Protocol 1.1
[REF9]	SOAP Messages with Attachments	SOAP Messages with Attachments
[REF10]	AS4 Profile of ebMS 3.0 Version 1.0	AS4 Profile of ebMS 3.0 Version 1.0
[REF11]	eSens - profile	http://wiki.ds.unipi.gr/display/ESENS/PR++AS4
[REF12]	eDelivery – Pmode Configuration	eDelivery – Pmode Configuration <i>(will be available at a later stage)</i>
[REF13]	http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/	XSDs for ebms3
[REF14]	http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/core/cs02/ebms_core-3.0-spec-cs-02.pdf	ebXML (Electronic Business using eXtensible Markup Language)

1.5. Acronyms

Acronym	Definition
ebMS	ebXML Messaging Service Specification
MEP	Message Exchange Pattern A Message Exchange Pattern describes the pattern of messages required by a communications protocol to establish or use a communication channel.
ebXML	Electronic Business XML Project to use XML to standardise the secure exchange of business data.
P-Mode	Processing Mode
MSH	Message Service Handler The MSH is an entity that is able to generate or process messages that conform to the ebMS specification, and which act in at least one of the two ebMS roles: Sender and Receiver. In terms of SOAP processing, an MSH is either a SOAP processor or a chain of SOAP processors. In either case, an MSH has to be able to understand the eb:Messaging header (qualified with the ebMS namespace).

2. INTERFACE FUNCTIONAL SPECIFICATION

2.1. The four corner model

In order to understand the Use Cases that will be described below it is important to explain the topology; i.e. the four – corner model.




Figure 1 - The four corner model

In this model we have the following elements:

- Corner One (C1): Backend C1 is the system that will use the sending AP (Access Point)
- Corner Two (C2): Sending Access Point C2
- Corner Three (C3): Receiving Access Point C3
- Corner Four (C4): Backend C4 is the system that will use the receiving AP (Access Point)

The JMS backend is described in this document. JMS (Java Message Service) is an API that provides the facility to create, send and read messages. It provides loosely coupled, reliable and asynchronous communication. JMS is also known as the standard for Java asynchronous messaging service. Messaging is a technique to enabling inter-application communications.

There are two types of messaging domains in JMS.

- Point-to-Point Messaging Domain
- Publisher/Subscriber Messaging Domain

The present JMS backend integration uses [Publisher/Subscriber Messaging pattern](#) where senders of messages, called publishers, do not plan the messages to be sent directly to specific receivers (called subscribers) but, instead, characterize published messages into classes without knowledge of which subscribers will be. Similarly, subscribers express interest in one or more classes and only receive the messages that are of their interest, without knowledge of which publishers are sending those messages. The intent of interest is done by means of a subscription.

2.2. Introduction to Domibus - AS4

Using as reference CEF DIGITAL⁴, Domibus is the Open Source project of the AS4 Access Point maintained by the European Commission. Third-party software vendors offer alternative implementations of the e-SENS AS4 Profile (commercial or open-source). Each software vendor also provides different added-value services from integration to the support of day-to-day operations. For safeguarding interoperability, CEF eDelivery encourages implementers to consult the list of software products that have passed the conformance tests by the European Commission of the eSENS AS4 profile⁵.

The sample software, Domibus, may be used to test other implementations of the AS4 profile or as a working solution in a production environment. The users of the sample implementation remain fully responsible for its integration with backend systems, deployment and operation. The support and maintenance of the sample implementation, as well as any other auxiliary services, are provided by the European Commission according to the terms defined in the CEF eDelivery Access Point Component Offering Description.

It is also important to comment on the PMode. A processing mode – or PMode – is a collection of parameters that determine how user messages are exchanged between a pair of Access Points with respect to Quality of Service, Transmission Mode and Error Handling. A PMode maps the recipient Access Point from the partyId, which represents the backend offices associated to this Access Point.

⁴ <https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus+++v3.3>

⁵ <https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/e-SENS+AS4+conformant+vendors>

3. INTERFACE BEHAVIOURAL SPECIFICATION

A JMS queue is a staging area that contains messages that have been sent and are waiting to be read. Contrary to what the name queue suggests, messages don't have to be received in the order in which they were sent. A JMS queue only guarantees that each message is processed only once.

Domibus queues are classified in 3 types:

- **Internal queues:** are accessed only by the core of the system
- **Notification queues:** are populated by the core of the system in order to be retrieved by the plugins deployed on the local access points
- **Backend queues:** are accessed by the backend themselves to either insert into or retrieve message from it.

Role of the plugins: plugins are the intermediate components that will allow incoming messages from corner 1 to enter corner 2 and outgoing messages to exit corner 3 to reach corner 4. These plugin must be compliant to Domibus specifications, and are specific to the backend implementation.

The following will introduce the queues chronologically, i.e. following the flow of message processed from corner 1 to corner 4.

The processing of a message, in short is processed as follows:

1. Corner 1 sends a message to an (input) plugin of corner 2.
2. The (input) plugin calls a set of API's exposed by the core to store the message into the database, generates a unique message ID and put that ID the internal dispatch queue referring to it.
3. The core of corner 2 discovers the message ID in the internal dispatch queue and the dispatcher sends it to the appropriate access point (corner 3).
4. The core of corner 3 stores it into the database, and creates a message into the internal notification queue referring to it
5. The notification listener of corner 3 discovers the message ID in the internal notification queue and makes it available into the notification dedicated queue of the appropriate (output) plugin of corner 3.
6. The (output) plug-in discovers the message ID into its dedicated queue and retrieves the message from the database
 - JMS (output) plugins will put it into the outQueue onto which its back-end (corner 4) is listening to.
 - Web service (output) plugin (Future implementation) will be send it directly to its back-end (retry will be done later in case of temporary unavailability of corner 4).




Figure 2 – Messages processing

The following section specifies the data format to be used to enable the following functions via JMS:

- Submit a message to the Access Point
- Push pending messages to a queue for retrieval

It uses the JMS MapMessage type in order to implement the request and response data formats for each of the functions mentioned above. The Meta data in each case will be set in the JMS message properties using name/value pairs and these will be outlined in each case.

3.1. JMS-Messages

Before going into the detail of the JMS queues it is important to describe the meaning of each tag included in the message that will be sent. It is important to note that most values (parties, services, actions, etc...) are specified by the use case and multilateral agreements and thus not to be chosen by the caller when the message is submitted. They are underlined in the table below.

Name	Description
<u>action</u>	This element is a string identifying an operation or an activity within a Service. Its actual semantics is beyond the scope of this specification. Action SHALL be unique within the Service in which it is defined. The value of the Action element is specified by the designer of the service.
<u>service</u>	This element identifies the service that acts on the message. Its actual semantics is beyond the scope of this specification. The designer of the service may be a standards organization, or an individual or enterprise. In other words, service element denotes the service that processes the message at the destination. As an example of what might exist in the Service element, consider the text urn:Invoice, denoting a message that should be processed by the invoice service.
<u>serviceType</u>	The Service element MAY contain a single @type attribute, that indicates how the parties sending and receiving the message will interpret the value of the element. There is no restriction on the value of the type attribute. If the type attribute is not present, the content of the Service element MUST be a URI.
conversationId	The Party initiating a conversation determines the value of the ConversationId element that SHALL be reflected in all messages pertaining to that conversation. The actual semantics of this value is beyond the scope of this specification. Implementations SHOULD provide a facility for mapping between their identification scheme and a ConversationId generated by another implementation.
messageId	This element has a value representing – for each message - a globally unique identifier. Note: In the Message_Id and Content_Id MIME headers, values are always surrounded by angle brackets. However references in mid: or cid: scheme URI's and the MessageId and RefToMessageId elements MUST NOT include these delimiters.
refToMessageId	This element occurs at most once. When present, it MUST contain the MessageId value for which the message is related.
agreementRef	AgreementRef is a string value that identifies the agreement that governs the exchange. The value of an AgreementRef element MUST be unique within a namespace mutually agreed by the two parties. This could be a concatenation of the From and To PartyId's values, a URI containing the Internet domain name of one of the parties, or a namespace offered and managed by some other naming or registry service. It is RECOMMENDED that the AgreementRef is a URI.
agreementRefType	This attribute indicates how the parties sending and receiving the message will interpret the value of the reference. There is no restriction on the value of the type attribute. If the type attribute is not present, the content of the eb:AgreementRef element MUST be a URI.
<u>fromRole</u>	This element occurs once, and identifies the authorized role (fromAuthorizedRole) of the Party sending (present as a child of the From element) the message. The value of the fromRole element is a non- empty string, with a default value of http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultRole . Other possible values are subject to partner agreement.
<u>toRole</u>	This element occurs once, and identifies the authorized role (toAuthorizedRole) of the Party receiving (present as a child of the To element) the message. The value of the toRole element is a non- empty string, with a default value of http://docs.oasis-

	open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultRole. Other possible values are subject to partner agreement.
messageType	A string representing the type of the message.
JMSCorrelationId	The JMSCorrelationID header field is used for linking one message with another. It typically links a reply message with its requesting message. JMSCorrelationID can hold a provider-specific message ID, an application-specific String object, or a provider-native byte[] value.
fromPartyId	Access Point C2. This element has a string value content that identifies a party, or that is one of the identifiers of this party who is sending the message.
fromPartyType	A string that identifies the type of the sender partyId. The type attribute indicates the domain of names to which the string in the content of the fromPartyId element belongs. It is RECOMMENDED that the value of the type attribute be a URI. It is further RECOMMENDED that these values be taken from the EDIRA , EDIFACT or ANSI ASC X12 registries. Technical specifications for the first two registries can be found at and [ISO6523] and [ISO9735], respectively.
toPartyId	Access Point C3. This element has a string value content that identifies a party, or that is one of the identifiers of this party. The one who is receiving the message.
toPartyType	A string that identifies the type of the receiver partyId. The type attribute indicates the domain of names to which the string in the content of the toPartyId element belongs. It is RECOMMENDED that the value of the type attribute be a URI. It is further RECOMMENDED that these values be taken from the EDIRA , EDIFACT or ANSI ASC X12 registries. Technical specifications for the first two registries can be found at and [ISO6523] and [ISO9735], respectively.
originalSender	Backend C1. This element has a string value content that identifies a party, or that is one of the identifiers of this party. Who is sending the message.
finalRecipient	Backend C2. This element has a string value content that identifies a party, or that is one of the identifiers of this party. Who is receiving the message.
protocol	The description of the protocol used. For the scenario described in this document it MUST be AS4.
totalNumberOfPayloads	Defines the number of payloads available in the message.
P1InBody (true/false)	Boolean that indicates if the payload is in the body of the AS4 message or not. If the payload is not in the body of the AS4 message it will be sent as attachment in the SOAP message.
putAttachmentInQueue	If true, all the payloads from the User Message will be stored as bytes in the JMS message. If false and Domibus is configured to save the payloads on the file system(property domibus.attachment.storage.location), the payloads file locations will be stored in the JMS message This property should be disabled for large file transfers.

Table 2 – JMS Message fields

The only mandatory rule is that only messageType=submitMessage messages may be put on the domibus.backend.jmsInQueue. All other queues (that go from the plugin to the backend) can be freely aggregated. I.e. if you only want one replyQueue you are free to send all success and errorMessages there.

3.2. JMS-Queues

3.2.1. [domibus.backend.jmsInQueue](#)

Description:

Submit a message from a Backend to Domibus. If a property is set in the plugin properties (jms-business-defaults.properties) but not in the message itself, the value from the properties file will be used.

Message type: `javax.jms.MapMessage`

Property name	Optional	Available in plugin properties	Notes
messageType	No	No	Value = submitMessage
messageId	Yes	No	Must be a globally unique Id
action	No	Yes	
conversationId	Yes	No	
JMSCorrelationId	No	No	
fromPartyId	No	Yes	
fromRole	No	Yes	
fromPartyType	No	Yes	
toPartyId	No	Yes	
toRole	No	Yes	
toPartyType	No	Yes	
originalSender	Yes	No	
finalRecipient	Yes	No	
service	No	Yes	
serviceType	Yes	Yes	Only optional if the service is untyped
protocol	Yes	No	Values other than AS4 or empty will raise an exception
refToMessageId	Yes	No	
agreementRef	Yes	Yes	
totalNumberOfPayloads	No	No	Outlining the total number of payloads, 0 payloads is valid
P1InBody (true/false)	Yes	Yes	If true, payload_1 will be sent in the body of the AS4 message. Only XML payloads may be sent in the AS4 message body.

putAttachmentInQueue (true/false)	Yes	Yes	If true, all the payloads from the User Message will be stored as bytes in the JMS message. If false and Domibus is configured to save the payloads on the filesystem (property domibus.attachment.storage.location), the payloads file locations will be stored in the JMS message. This property should be disabled for large file transfers.
--	-----	-----	---

Table 3 - `domibus.backend.jmsInQueue` message fields

Payload handling:

The following properties should be set for each payload in the message. In the list below, the string “[NUM]” of each property name should be replaced with a numerical value representing each payload. The payload with the prefix `payload_1` is transported inside the body of the AS4 message if the property `p1InBody` is set to true.

Each payload can: either be sent in byte format and set in the `MapMessage` using the `setBytes` method of the `MapMessage` class or an URL from where the payload can be downloaded by the Domibus Access Point. Each payload should be identified by the property `payload_[NUM]`.

The following properties can be set for each payload using the `setStringProperty` method of the `MapMessage` class:

- `payload_[NUM]_description`: A description of the payload
- `payload_[NUM]_MimeContentID`: For example the `MimeContentID` for the first payload will be identified by the property `payload_1_MimeContentID`. This is the payload contentId. Setting it is required if the pmode payload profiling is used. If unset Domibus generates a UUID for it.
- `payload_[NUM]_MimeType`: The mime type of the payload. If not provided the mime type `application/octet-stream` is assumed
- `payload_[NUM]_FileName`: The file location of the payload, if `putAttachmentInQueue` is set.

Property Handling

Message properties are handled in the following way:

- Properties named `property_[NAME]` are put into the outgoing message using `[NAME]` as key inside the AS4 message.
- For each `property_[NAME]` property there MAY be a corresponding `propertyType_[NAME]` property set. The corresponding value MAY be NULL, indicating an untyped property. Older AS4 implementations which do not have implemented the latest errata MIGHT REJECT messages where a property type is NOT NULL

3.2.2. [domibus.backend.jms.replyQueue](#)

Description: The result of the submit operation and contains either the `messageId` or an error. The `messageId` is (usually) generated by Domibus. If the submission is rejected, no `messageId` is generated. Additionally, there is no guarantee that the set `MessageId` of a rejected message can be read. This message has to be correlated using the `JMSCorrelationID`. Corner 2 reports back to corner 1 about the success/failure of an intended message submission.

Message type: `javax.jms.Message`

Property name	Optional	Notes
messageType	No	Value=submitResponse
messageId	Yes	null, if there is an errorDetail
errorDetail	Yes	null, if there is a messageId

Table 4 - domibus.backend.jms.replyQueue message fields

Description: A message has been successfully sent to another AS4 Access Point. The status changes to messageSent when the message has been sent from C2 to C3. The reason why this is a different logical queue is to allow better configuration options, i.e. you might want to send those messages to a monitoring system (or dev/null) and not to the back office application. As this is only a logical queue, nothing prevents it from using the same physical queue if all of those messages have the same recipient.

Property name	Optional	Notes
messageType	No	Value=messageSent
messageId	No	

Table 5 - domibus.backend.jms.replyQueue message fields

Payload handling: N/A

Property Handling: N/A

3.2.3. domibus.backend.jms.outQueue

Description: submit a message from Domibus (corner 3) to a backend (corner4)

Message type: javax.jms.MapMessage

Property name	Optional	Notes
messageType	No	Value = incomingMessage
messageId	No	Must be a globally unique Id
action	No	
conversationId	No	
fromPartyId	No	
fromRole	No	
fromPartyType	No	
toPartyId	No	
toRole	No	
toPartyType	No	
originalSender	Yes	
finalRecipient	Yes	
service	No	

serviceType	Yes	Only optional if the service is untyped
protocol	No	Value = AS4
refToMessageId	Yes	
agreementRef	Yes	
totalNumberOfPayloads	No	outlining the total number of payloads, 0 payloads is valid

Table 6 - `domibus.backend.jms.outQueue` message fields

Payload handling:

The following properties are set for each payload in the message. In the list below, the string “[NUM]” of each property name is replaced with a numerical value representing each payload. If a payload has been transported in the message body of the corresponding AS4 message, this is always the payload with the prefix `payload_1`. Each payload is sent in byte format. Each payload is identified by the property `payload_[NUM]`.

The following properties may be available for each payload:

- `payload_[NUM]_description`: A description of the payload
- `payload_[NUM]_MimeContentID`: For example the `MimeContentID` for the first payload will be identified by the property `payload_1_MimeContentID`. This is the payload `contentId`. Setting it is required if the `pmode` payload profiling is used. If unset Domibus generates a UUID for it.
- `payload_[NUM]_MimeType`: The mime type of the payload
- `payload_[NUM]_FileName`: The file location of the payload, if `putAttachmentInQueue` is set.

Property Handling

Message properties are handled in the following way:

- Properties named `[NAME]` are put into the incoming message using `property_[NAME]` as key inside the JMS message
- For each `property_[NAME]` property there is a corresponding `propertyType_[NAME]` property set. The corresponding value MAY be NULL, indicating an untyped property. Older AS4 implementations which do not have implemented the latest errata will only ever send untyped properties

3.2.4. `domibus.backend.jms.errorNotifyProducer`

Description: A message that was accepted as submission could not be sent to the recipient.

Message type: `javax.jms.Message`

Property name	Optional	Notes
messageType	No	Value= <code>messageSendFailure</code>
messageId	No	
errorCode	No	The ebMS3 error code of the corresponding error
errorDetail	No	A textual description of the error

Table 7 - `domibus.backend.jms.errorNotifyProducer` message fields

Payload handling: N/A

3.2.5. domibus.backend.jms.errorNotifyConsumer

Description: An incoming message was rejected because of an error or agreement violation. To generate such a message, the Domibus Access Point must, at least, be able to determine the intended recipient for the original message. If this is not possible, no messageReceiveFailure will be generated.

Message type: `javax.jms.Message`

Property name	Optional	Notes
messageType	No	Value=messageReceiveFailure
messageId	No	
errorCode	No	The ebMS3 error code of the corresponding error
errorDetail	No	A textual description of the error
endPoint	Yes	The internet address of the access point that tried to send the message

Table 8 - domibus.backend.jms.errorNotifyConsumer message fields

Payload handling: N/A

Property Handling: N/A

4. ANNEXE 1 – INTERFACE POLICY SPECIFICATION

The Party initiating a conversation MUST determine the value of the ConversationId element that is reflected in all messages pertaining to that conversation. The actual semantics of this value is beyond the scope of this specification. Implementations SHOULD provide a facility for mapping between their identification scheme and a ConversationId generated by another implementation.

The following details a simple function for submitting a message in the correct format to a queue where it will be picked up by a MessageListener on the Access Point.

```

package eu.domibus.plugin.jms;
import org.apache.activemq.ActiveMQConnectionFactory;
import org.junit.Ignore;
import org.junit.Test;
import javax.jms.*;
import javax.naming.NamingException;
public class MessageSender {
    @Test
    @Ignore //This is just an example the used PMode does not actually exist
    public void sendMessage() throws NamingException, JMSException {
        ActiveMQConnectionFactory connectionFactory = new
ActiveMQConnectionFactory("tcp://localhost:61616");//default port of activeMQ
        Connection connection = null;
        MessageProducer producer = null;
        connection = connectionFactory.createConnection("domibus", "changeit"); //username and password of
the default JMS broker
        Session session = connection.createSession(false, Session.AUTO_ACKNOWLEDGE);
        Destination destination = session.createQueue("domibus.backend.jms.inQueue");
        producer = session.createProducer(destination);
        producer.setDeliveryMode(DeliveryMode.NON_PERSISTENT);
        MapMessage messageMap = session.createMapMessage();
        // Declare message as submit
        messageMap.setStringProperty("messageType", "submitMessage");
        // Set up the Communication properties for the message
        messageMap.setStringProperty("service", "demoService");
        messageMap.setStringProperty("action", "demoAction");
        messageMap.setStringProperty("conversationId", "");
        messageMap.setStringProperty("fromPartyId", "GW1");
        messageMap.setStringProperty("fromPartyIdType", "urn:oasis:names:tc:ebcore:partyid-type:iso3166-
1");
        messageMap.setStringProperty("fromRole", "buyer");
        messageMap.setStringProperty("toPartyId", "GW1");
        messageMap.setStringProperty("toPartyIdType", "urn:oasis:names:tc:ebcore:partyid-type:iso3166-1");
        messageMap.setStringProperty("toRole", "seller");
        messageMap.setStringProperty("originalSender", "sending_buyer_id");
        messageMap.setStringProperty("finalRecipient", "receiving_seller_id");
        messageMap.setStringProperty("serviceType", "");
        messageMap.setStringProperty("protocol", "AS4");
        messageMap.setStringProperty("refToMessageId", "");
        messageMap.setStringProperty("agreementRef", "");
        messageMap.setJMSCorrelationID("MESS1");
        //Set up the payload properties
        messageMap.setStringProperty("totalNumberOfPayloads", "3");
        messageMap.setStringProperty("payload_1_mimeContentId", "cid:cid_of_payload_1");
        messageMap.setStringProperty("payload_2_mimeContentId", "cid:cid_of_payload_2");
        messageMap.setStringProperty("payload_3_mimeContentId", "cid:cid_of_payload_3");
        messageMap.setStringProperty("payload_1_mimeType", "application/xml");
        messageMap.setStringProperty("payload_2_mimeType", "application/xml");
        messageMap.setStringProperty("payload_3_mimeType", "application/xml");
        messageMap.setStringProperty("payload_1_description", "description1");
        messageMap.setStringProperty("payload_2_description", "description2");
        messageMap.setStringProperty("payload_3_description", "description3");
        messageMap.setStringProperty("payload_1_fileName", "filenameLocation1");
        messageMap.setStringProperty("payload_2_fileName", "filenameLocation2");
        messageMap.setStringProperty("payload_3_fileName", "filenameLocation3");
        String payl = "<XML><test></test></XML>";
        byte[] payload = payl.getBytes();
        messageMap.setBytes("payload_1", payload);
        messageMap.setBytes("payload_2", payload);
        messageMap.setBytes("payload_3", payload);
        producer.send(messageMap);
        connection.close();
    }
}

```

5. ANNEX 2 - ERRORS CODES TABLE

The following tables summarize all possible errors returned by the Access Point services:

Error Code	Short Description	Recommended Severity	Category Value	Description or Semantics
EBMS_0001	ValueNotRecognized	failure	Content	Although the message document is well formed and schema valid, some element/attribute contains a value that could not be recognized and therefore could not be used by the MSH.
EBMS_0002	FeatureNotSupported	warning	Content	Although the message document is well formed and schema valid, some element/attribute value cannot be processed as expected because the related feature is not supported by the MSH.
EBMS_0003	ValueInconsistent	failure	Content	Although the message document is well formed and schema valid, some element/attribute value is inconsistent either with the content of other element/attribute, or with the processing mode of the MSH, or with the normative requirements of the ebMS specification.
EBMS_0004	Other	failure	Content	
EBMS_0005	ConnectionFailure	failure	Communication	The MSH is experiencing temporary or permanent failure in trying to open a transport connection with a remote MSH.
EBMS_0006	EmptyMessagePartitionChannel	warning	Communication	There is no message available for pulling from this MPC at this moment.
EBMS_0007	MimeInconsistency	failure	Unpackaging	The use of MIME is not consistent with the required usage in this specification.
EBMS_0008	FeatureNotSupported	failure	Unpackaging	Although the message document is well formed and schema valid, the presence or absence of some element/ attribute is not consistent with the capability of the MSH, with respect to supported features.
EBMS_0009	InvalidHeader	failure	Unpackaging	The ebMS header is either not well formed as an XML document, or does not conform to the ebMS packaging rules.
EBMS_0010	ProcessingModeMismatch	failure	Processing	The ebMS header or another header (e.g. reliability, security) expected by the MSH is not compatible with the expected content, based on the associated P-Mode.
EBMS_0011	ExternalPayloadError	failure	Content	The MSH is unable to resolve an external payload reference (i.e. a Part that is not contained within the ebMS Message, as identified by a PartInfo/href URI).
EBMS_0101	FailedAuthentication	failure	Processing	The signature in the Security header intended for the "ebms" SOAP actor could not be validated by the Security module.
EBMS_0102	FailedDecryption	failure	Processing	The encrypted data reference the Security header intended for the "ebms" SOAP actor could not be decrypted by the Security Module.
EBMS_0103	PolicyNoncompliance	failure	Processing	The processor determined that the message's security methods, parameters, scope or other security policy-level requirements or agreements were not satisfied.
EBMS_0201	DysfunctionalReliability	failure	Processing	Some reliability function as implemented by the Reliability module is not operational, or the reliability state associated with this message sequence is not valid.
EBMS_0202	DeliveryFailure	failure	Communication	Although the message was sent under Guaranteed delivery requirement, the Reliability module could not get assurance that the message was properly delivered, in spite of resending efforts.
EBMS_0301	MissingReceipt	failure	Communication	A Receipt has not been received for a message that was previously sent by the MSH generating this error

Error Code	Short Description	Recommended Severity	Category Value	Description or Semantics
EBMS_0302	InvalidReceipt	failure	Communication	A Receipt has been received for a message that was previously sent by the MSH generating this error, but the content does not match the message content (e.g. some part has not been acknowledged, or the digest associated does not match the signature digest, for NRR).
EBMS_0303	DecompressionFailure	failure	Communication	An error occurred during the decompression
EBMS_0020	RoutingFailure	failure	Processing	An Intermediary MSH was unable to route an ebMS message and stopped processing the message.
EBMS_0021	MPCCapacityExceeded	failure	Processing	An entry in the routing function is matched that assigns the message to an MPC for pulling, but the intermediary MSH is unable to store the message with this MPC
EBMS_0022	MessagePersistenceTimeout	failure	Processing	An intermediary MSH has assigned the message to an MPC for pulling and has successfully stored it. However the intermediary set a limit on the time it was prepared to wait for the message to be pulled, and that limit has been reached.
EBMS_0023	MessageExpired	warning	Processing	An MSH has determined that the message is expired and will not attempt to forward or deliver it.
EBMS_0030	BundlingError	failure	Content	The structure of a received bundle is not in accordance with the bundling rules.
EBMS_0031	RelatedMessageFailed	failure	Processing	A message unit in a bundle was not processed because a related message unit in the bundle caused an error.
EBMS_0040	BadFragmentGroup	failure	Content	A fragment is received that relates to a group that was previously rejected.
EBMS_0041	DuplicateMessageSize	failure	Content	A fragment is received but more than one fragment message in a group of fragments specifies a value for this element.
EBMS_0042	DuplicateFragmentCount	failure	Content	A fragment is received but more than one fragment message in a group of fragments specifies a value for this element.
EBMS_0043	DuplicateMessageHeader	failure	Content	A fragment is received but more than one fragment message in a group of fragments specifies a value for this element.
EBMS_0044	DuplicateAction	failure	Content	A fragment is received but more than one fragment message in a group of fragments specifies a value for this element.
EBMS_0045	DuplicateCompressionInfo	failure	Content	A fragment is received but more than one fragment message in a group of fragments specifies a value for a compression element.
EBMS_0046	DuplicateFragment	failure	Content	A fragment is received but a previously received fragment message had the same values for GroupId and FragmentNum
EBMS_0047	BadFragmentStructure	failure	Unpackaging	The href attribute does not reference a valid MIME data part, MIME parts other than the fragment header and a data part are in the message. are added or the SOAP Body is not empty.
EBMS_0048	BadFragmentNum	failure	Content	An incoming message fragment has a value greater than the known FragmentCount.
EBMS_0049	BadFragmentCount	failure	Content	A value is set for FragmentCount, but a previously received fragment had a greater value.
EBMS_0050	FragmentSizeExceeded	warning	Unpackaging	The size of the data part in a fragment message is greater than Pmode[.Splitting.FragmentSize
EBMS_0051	ReceiveIntervalExceeded	failure	Unpackaging	More time than Pmode[.Splitting.JoinInterval has passed since the first fragment was received but not all other fragments are received.
EBMS_0052	BadProperties	warning	Unpackaging	Message properties were present in the fragment SOAP header that were not specified in Pmode[.Splitting.RoutingProperties
EBMS_0053	HeaderMismatch	failure	Unpackaging	The eb3:Message header copied to the fragment header does not match the eb3:Message header in the reassembled source message.
EBMS_0054	OutOfStorageSpace	failure	Unpackaging	Not enough disk space available to store all

Error Code	Short Description	Recommended Severity	Category Value	Description or Semantics
				(expected) fragments of the group.
EBMS_0055	DecompressionError	failure	Processing	An error occurred while decompressing the reassembled message.
EBMS_0060	ResponseUsingAlternateMEP	Warning	Processing	A responding MSH indicates that it applies the alternate MEP binding to the response message.

Table 9 - Annex 2 - Errors codes table

6. ANNEXE 3 – DOCUMENT PARTS



(eDelivery)(Domibus)
(ICD)(Default JMS Pl

7. LIST OF FIGURES

Figure 1 - The four corner model	8
Figure 2 – Messages processing	11

8. LIST OF TABLES

Table 1 - Interface escribed	4
Table 2 – JMS Message fields	13
Table 3 - domibus.backend.jmsInQueue message fields	15
Table 4 - domibus.backend.jms.replyQueue message fields	16
Table 5 - domibus.backend.jms.replyQueue message fields	16
Table 6 - domibus.backend.jms.outQueue message fields.....	17
Table 7 - domibus.backend.jms.errorNotifyProducer message fields	17
Table 8 - domibus.backend.jms.errorNotifyConsumer message fields	18
Table 9 - Annex 2 - Errors codes table.....	22

9. CONTACT INFORMATION

CEF Support Team

By email: CEF-EDELIVERY-SUPPORT@ec.europa.eu

By phone: +32 2 299 09 09

- Standard Service: 8am to 6pm (Normal EC working Days)
- Standby Service*: 6pm to 8am (Commission and Public Holidays, Weekends)

** Only for critical and urgent incidents and only by phone*