



EUROPEAN COMMISSION

DIGIT
Connecting Europe Facility

Domibus 4.2.3

Quick Start Guide

© European Union, 2021

Reuse of this document is authorised provided the source is acknowledged. The Commission's reuse policy is implemented by Commission Decision 2011/833/EU of 12 December 2011 on the reuse of Commission documents.

Date: 04/08/2021

Document Approver(s):

| Approver Name | Role |
|---------------|-----------------|
| FERIAL Adrien | Project Manager |
| | |
| | |

Document Reviewers:

| Reviewer Name | Role |
|----------------------------------|--------------------------|
| Amar DEEP | CEF Support Office |
| BACIU Cosmin | Domibus Technical Leader |
| DRAGUSANU Ioana | Developer |
| AEBY Caroline and Chaouki BERRAH | Technical Writers |

Summary of Changes:

| Version | Date | Created by | Short Description of Changes |
|---------|------------|---------------------------------|---|
| V0.1 | 15/09 | Cedric EDELMAN | Initial version based on the QSG of Domibus 3.1.1 |
| V1.0 | 15/09 | Adrien FERIAL | Update for Domibus 3.2 |
| V1.1 | 23/06/2017 | Tiago MIGUEL, C. BACIU | Update for Domibus 3.3-RC1 |
| V1.2 | 27/07/2017 | Chaouki BERRAH | Script name change |
| V1.3 | 13/09/2017 | Chaouki BERRAH | Update for Domibus 3.3 FR |
| V1.4 | 18/09/2017 | Chaouki BERRAH | Version number Domibus release=>'X.Y.Z'. |
| V1.5 | 19/09/2017 | Chaouki BERRAH | Tomcat DB config. Pmode updated. |
| V1.6 | 03/10/2017 | Caroline AEBY Chaouki BERRAH | Cosmin's comments taken into account. |
| V1.7 | 09/10/2017 | CEF Support | List of reviewers updated. |
| V1.8 | 28/11/2017 | CEF Support | Domibus 3.3.1: admin console changes (lockout policy + JMS Monitoring). |
| V1.9 | 13/12/2017 | Chaouki BERRAH | @localhost added in MYSQL statement |
| V2.0 | 21/12/2017 | CEF Support | Corrected some inconsistencies |
| V2.1 | 08/03/2018 | Chaouki BERRAH | Update for Version 3.3.2 + deletion scripts |
| V2.2 | 20/03/2018 | CEF Support | Reuse notice added |
| V2.3 | 20/06/2018 | CEF Support | Update for Domibus version 3.3.4 |
| V2.4 | 23/07/2018 | Chaouki BERRAH | Update for Domibus version 4.0-RC1 |
| V2.5 | 26/07/2018 | Chaouki BERRAH | PMODE updated |
| V2.6 | 20/08/2018 | C. BACIU/ C. COMANICI | Updates for 4.0 FR |
| 2.7 | 26/09/2018 | Caroline AEBY | Contact information update |
| 2.8 | 02/10/2018 | Chaouki BERRAH | Prerequisites changes |
| 2.9 | 04/12/2018 | Caroline AEBY | 4.0.1 updates |
| 3.0 | 11/02/2019 | Caroline AEBY | 4.0.2 updates |
| 3.1 | 19/03/2019 | Chaouki BERRAH | Tomcat version change/ Wildfly 9 removed +4.1-RC1 updated |
| 3.2 | 15/07/2019 | Caroline AEBY | 4.1-RC1 => 4.1 |

| | | | |
|-------|------------|-------------------------------|--|
| 3.3 | 16/09/2019 | Caroline AEBY | 4.1=>4.1.1 |
| 3.4 | 30/09/2019 | Chaouki BERRAH | General Update + DB and servers supported versions updated |
| 3.5 | 05/11/2019 | Caroline AEBY | 4.1.2 + Oracle 12g => Oracle 12c |
| 3.6 | 04/02/2020 | Caroline AEBY | 4.1.2 => 4.1.3 |
| 3.6.1 | 08/05/2020 | Caroline AEBY | Domibus 4.2 – supported versions change for Tomcat, Wildfly, WebLogic and MySQL |
| 4.0 | 21/08/2020 | Chaouki BERRAH | OpenJDK support added for Tomcat and Wildfly. Wildfly upgraded to version 20.0.1.Final |
| 4.1 | 09/09/2020 | Caroline AEBY | Oracle 19C also supported |
| 4.2 | 18/09/2020 | Cosmin BACIU Caroline AEBY | Updated plugin deployment procedure Domibus 4.2 RC release |
| 4.3 | 18/11/2020 | Caroline AEBY | Oracle JAVA JRE (not IBM) |
| 4.4 | 30/11/2020 | Cosmin BACIU Caroline AEBY | Domibus 4.2. FR review |
| 4.6 | 16/03/2021 | Caroline AEBY | Domibus 4.2.1 version + open JDK version |
| 4.7 | 12/04/2021 | Caroline AEBY | Oracle supported version: Oracle 12c R2 |
| 4.8 | 18/05/2021 | Caroline AEBY | Domibus 4.2.2 version |
| 4.9 | 04/08/2021 | Caroline AEBY | Domibus 4.2.3 version |

CONTENTS

| | |
|--|-----------|
| INTRODUCTION..... | 5 |
| PURPOSE OF THIS GUIDE | 6 |
| PREREQUISITES | 8 |
| CONFIGURE YOUR ENVIRONMENT..... | 9 |
| 1.1. Package Overview | 9 |
| 1.1.1. Domibus-distribution-X.Y.Z-tomcat-full.zip..... | 9 |
| 1.1.2. Domibus-distribution-X.Y.Z-sample-configuration-and-testing.zip | 10 |
| 1.2. Tomcat Standalone Access Point | 11 |
| TESTING | 16 |
| Default plugins | 16 |
| ANNEX 1: PARAMETERS..... | 17 |
| PMODES/DOMIBUS-GW-SAMPLE-PMODE-BLUE.XML..... | 17 |
| PMODES/DOMIBUS-GW-SAMPLE-PMODE-RED.XML | 17 |
| ANNEX 2: FIREWALL SETTINGS..... | 18 |
| ANNEX 3: PROCESSING MODE | 21 |
| ANNEX 4: DOMIBUS PCONF TO EBMS3 PMODE MAPPING | 25 |
| ANNEX 5: INTRODUCTION TO AS4 SECURITY | 31 |
| CONTACT INFORMATION..... | 33 |

INTRODUCTION

The CEF eDelivery Access Point (AP) Domibus implements a standardised message exchange protocol that ensures interoperable, secure and reliable data exchange.

Domibus is the Open Source project of the AS4 Access Point maintained by the European Commission.

The current release of Domibus supports Tomcat, WebLogic and WildFly and contains the following archives, where X.Y.Z refers to the version number release (e.g.: X.Y.Z=4.2.3):

- **domibus-distribution-X.Y.Z-tomcat-full.zip** containing the full Tomcat distribution. Default Web Service plugin is also included in this archive and deployed as the default plugin.
- **domibus-distribution-X.Y.Z-tomcat-war.zip** containing the Domibus war for Tomcat.
- **domibus-distribution-X.Y.Z-tomcat-configuration.zip** containing the Domibus configuration files for Tomcat.
- **domibus-distribution-X.Y.Z-weblogic-war.zip** containing the Domibus war for WebLogic.
- **domibus-distribution-X.Y.Z-weblogic-configuration.zip** containing the Domibus configuration files for WebLogic.
- **domibus-distribution-X.Y.Z-wildfly20-full.zip** containing the full WildFly distribution. Default Web Service plugin is also included in this archive and deployed as the default plugin.
- **domibus-distribution-X.Y.Z-wildfly20-war.zip** containing the Domibus war for WildFly.
- **domibus-distribution-X.Y.Z-wildfly20-configuration.zip** containing the Domibus configuration files for Wildfly 20.
- **domibus-distribution-X.Y.Z-sample-configuration-and-testing.zip** containing a sample of certificates, PMode configuration files and test SoapUI project.
- **domibus-distribution-X.Y.Z-sql-scripts.zip** containing SQL scripts (full and migration) for the creation and manipulation of the database schema as well as deletion scripts for MySQL and Oracle. With the deletion scripts, users can delete information relevant to a message sent or received during a predefined period.
- **domibus-distribution-X.Y.Z-default-jms-plugin.zip** containing the binaries and configuration file for the JMS plugin.
- **domibus-distribution-X.Y.Z-default-ws-plugin.zip** containing the binaries and configuration file for the Web Service plugin.
- **domibus-distribution-X.Y.Z-default-fs-plugin.zip** containing the binaries and configuration file for the File System plugin.

PURPOSE OF THIS GUIDE

This release contains the AS4 Access Point of the CEF eDelivery Digital Service Infrastructure (DSI). For more information about this release, please refer to [CEF Digital](#).

This release of the CEF eDelivery Access Point is the result of significant collaboration among different EU policy projects, IT delivery teams and the CEF eDelivery DSI. Nevertheless, this eDelivery release is fully reusable by any other policy domain of the EU.

This release supports:

- Tomcat 9.x
- WebLogic Version 12.2.1.4 (tested versions, future versions might also work)
- WildFly 20.0.x (tested versions, future versions might also work)
- Oracle 12c R2 and Oracle 19c
- MySQL 8

In this guide, we are covering Tomcat/MySQL configuration.

For Domibus installation on WildFly or WebLogic or more information on Domibus configuration in general, please read the Administration Guide available on the release page of Domibus.

This Document is a guide for the deployment of Domibus in Static Discovery mode. For Dynamic Discovery, please refer to the full [Administration guide](#).

We will guide you to setup two Tomcat standalone Access Points, deployed on different machines, to exchange B2B documents securely over AS4 by:

- Deploying and configuring both Access Points (blue and red)
- Configuring processing mode files for both AS4 Access Points
- Using the provided AS4 Access Points certificates
- Setup the Access Points blue and red for running test cases (see [Testing section](#))




Figure 1 - Installation on two different machines

Remarks:

- *The same procedure can be extended to a third (or more) Access Point.*
- *This guide does not cover the preliminary network configuration allowing communication between separate networks (e.g.: Proxy setup).*

PREREQUISITES

- Oracle Java runtime environment (JRE) **or** Oracle OpenJDK11:

- Oracle JRE version 8 for Tomcat, WildFly and WebLogic :

<http://www.oracle.com/technetwork/java/javase/downloads/index.html>

- Oracle OpenJDK 11 up to version 11.0.9.1+1 for Tomcat and WildFly only, not WebLogic:

<https://openjdk.java.net/projects/jdk/11/>

- One of the supported Database Management Systems :

○ MySQL 8 *

○ Oracle 12c R2 or Oracle 19c *

* Version tested, future versions might work

Please install the above software on your host machine. For further information and installation details, refer to the manufacturers' websites.

CONFIGURE YOUR ENVIRONMENT

1.1. Package Overview

1.1.1. Domibus-distribution-X.Y.Z-tomcat-full.zip

Download the Domibus X.Y.Z distribution from CEF Digital:

<https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus>

This package has the following structure:

| Name | Size |
|------------------|------------|
| domibus | 69 132 135 |
| sql-scripts | 120 952 |
| changelog.txt | 9 968 |
| upgrade-info.txt | 36 934 |

Figure 2 - Package content

- <CEF-eDelivery path>/domibus/bin contains the executable batch file (Windows) and shell script (Linux) which are required to launch the Access Point.
- <CEF-eDelivery path>/sql-scripts contains the required application SQL code that needs to be executed on the MySQL database (and scripts for Oracle DB).

Remark:

<CEF-eDelivery path> is the location where you extracted the downloaded package.

- <CEF-eDelivery path>/domibus contains:

| Name | Size |
|---------------|------------|
| bin | 768 519 |
| conf | 358 824 |
| lib | 7 335 433 |
| logs | 0 |
| temp | 0 |
| webapps | 60 586 207 |
| LICENSE | 58 068 |
| NOTICE | 1 489 |
| RELEASE-NOTES | 6 913 |
| RUNNING.txt | 16 682 |

Figure 3 - eDelivery path/domibus content

- **conf** folder where you will find the *configuration files* (.xml used to administer your Tomcat and the default domibus configuration files)
- **logs** folder where the logs are stored
- **webapps** folder where the WAR files are stored

| Name | Size |
|-------------|------------|
| domibus.war | 60 586 207 |

Figure 4 - Domibus WAR file

- <CEF-eDelivery path>/domibus/conf/domibus contains domibus configuration files:

| Name | Size |
|--------------------|---------|
| internal | 9 895 |
| plugins | 113 241 |
| policies | 17 634 |
| domibus.properties | 6 318 |
| logback.xml | 5 121 |

Figure 5 - Domibus configuration files

1.1.2. Domibus-distribution-X.Y.Z-sample-configuration-and-testing.zip

Download the Domibus X.Y.Z configuration files sample from CEF Digital site:

<https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus>

This package has the following structure and contains pre-configured files for Domibus:

| Name | Size |
|------|---------|
| conf | 16 602 |
| test | 200 852 |

Figure 6 - Pre-configured files for Domibus

- <CEF-eDelivery path>/test contains a SOAP UI test project.
- <CEF-eDelivery path>/domibus/conf/pmodes contains two AS4 processing modes xml files (one for blue and other for red Access Point) pre-configured to use compression, payload encryption, message signing and non-repudiation, according to the [eDelivery AS4 profile](#).
- <CEF-eDelivery path>/domibus/conf/domibus keystores contains a keystore (with the private keys of Access Point blue and Access Point red) and a truststore (with the public keys of Access Point blue and Access Point red) that can be used by both Access Points. Note that the keystore contains the private keys of both Access Points blue and red. This setup is not secure and is used for demonstration purpose only. In production, the private key should only be known, and deployed in the keystore of its owner (one participant). For this test release, each Access Point uses self-signed certificates. Please refer to [Annex 5](#) for more information about AS4 security.

Remark:

The **/conf** folder in the sample archive should be unzipped in <CEF-eDelivery path>/domibus that already exists by merging it with its content.

1.2. Tomcat Standalone Access Point

As described in the purpose of this guide, we need to configure two Access Points running on two separate machines. Therefore, the procedure below would need to be applied on both machines *Hostname "blue"* (<blue_hostname>:8080) and *Hostname "red"* (<red_hostname>:8080).

For this step, you will have to use the following resources (all binaries can be downloaded on <https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus>):

- **domibus-distribution-X.Y.Z-tomcat-full.zip**

1. Unzip the archive:

- a. Unzip **domibus-distribution-X.Y.Z-tomcat-full.zip** to a location on your physical machine: *cef_edelivery_path*.

| Name | Size |
|------------------|------------|
| domibus | 66 739 870 |
| sql-scripts | 70 415 |
| changelog.txt | 3 045 |
| upgrade-info.txt | 6 600 |

2. Prepare MySQL the database:

Add MySQL JDBC driver, available on MySQL official web site in the folder *cef_edelivery_path/domibus/lib*.

Remark:

The version of the JDBC driver has to be mysql-connector-java-5.1.40.jar or higher.

Edit the properties file *cef_edelivery_path/conf/domibus/domibus.properties* and adjust the highlighted parts in the text below according to your environment. The properties associated to the database configuration are pre-configured, for the MySQL database:

```
# ----- Database -----
#Database server name
domibus.database.serverName=localhost

#Database port
domibus.database.port=3306

#XA properties
```

```

domibus.datasource.xa.property.user=edelivery_user
domibus.datasource.xa.property.password=edelivery_password
#MySQL

domibus.datasource.xa.property.url=jdbc:mysql://${domibus.database.serverName}:${domibus.database.port}/ domibus_schema?pinGlobalTxToPhysicalConnection=true

#Non-XA Datasource
domibus.datasource.url=jdbc:mysql://${domibus.database.serverName}:${domibus.database.port}/do
mibus_schema?useSSL=false

domibus.datasource.user=edelivery_user
domibus.datasource.password=edelivery_password

```

3. Configure your Keystore based on section “Introduction to AS4 security” later in this document.
4. Set JVM parameters:

Domibus expects a single environment variable **domibus.config.location**, pointing towards the *cef_edelivery_path/conf/domibus* folder.

You can do this by editing the first command lines of *cef_edelivery_path\domibus\bin\setenv.bat* (Windows) or *cef_edelivery_path/domibus/bin/setenv.sh* (Linux). Set **CATALINA_HOME** equal to the absolute path of the installation *cef_edelivery_path/domibus*.

- For Windows : edit *cef_edelivery_path\domibus\bin\setenv.bat* by adding the following:

```

...
set CATALINA_HOME=cef_edelivery_path\domibus
set CATALINA_TMPDIR=<path to _tmp directory>
set JAVA_OPTS=%JAVA_OPTS% -Dfile.encoding=UTF-8 -Xms128m -Xmx1024m -XX:PermSize=64m
set JAVA_OPTS=%JAVA_OPTS% -Ddomibus.config.location=%CATALINA_HOME%\conf\domibus
...

```

- For Linux : edit *cef_edelivery_path/domibus/bin/setenv.sh* by adding the following:

```

...
export CATALINA_HOME=cef_edelivery_path/domibus
export CATALINA_TMPDIR=<path to _tmp directory>
export JAVA_OPTS="$JAVA_OPTS -Xms128m -Xmx1024m "
export JAVA_OPTS="$JAVA_OPTS -Ddomibus.config.location=$CATALINA_HOME/conf/domibus"
...

```

5. Launch the Domibus application:

- For Windows :

```

cd cef_edelivery_path\domibus\bin\
startup.bat

```

- For Linux :

```

cd cef_edelivery_path /domibus/bin/chmod u+x *.sh ./startup.sh

```

6. Display the Domibus home page on your browser: <http://localhost:8080/domibus>.
(By default: User = **admin**; Password = **123456**)

Remark:

You will be asked to change the default password when logging in for the first time.

If you can access the page, it means the deployment was successful.



Figure 7 - Domibus administration page

Remarks:

- To allow the remote application to send a message to this machine, you would need to create a dedicated rule (to allow this port) from your local firewall (cf. annex "[Firewall Settings](#)").
- If you intend to install both Access Points on the same server, you will need to change the ports of the red Access Point and create a separate database schema, update the `domibus.properties` file and change the ActiveMQ ports before starting the server to avoid conflicts.

7. Upload PModes

Edit the two PMode files `<CEF-eDelivery path>/domibus/conf/domibus/pmodes/domibus-gw-sample-pmode-blue.xml` and `domibus-gw-sample-pmode-red.xml`, and replace `<blue_hostname>` and `<red_hostname>` with their real hostnames or IPs:

```
<party name="red_gw"
      endpoint="http://<red_hostname>:8080/domibus/services/msh">
      <identifier partyId="domibus-red" partyIdType="partyTypeUrn"/>
</party>
<party name="blue_gw"
      endpoint="http://<blue_hostname>:8080/domibus/services/msh">
      <identifier partyId="domibus-blue" partyIdType="partyTypeUrn"/>
</party>
```

Figure 8 - PMode view

For more details about the provided PMode, please see [Annex 3](#).

Upload the PMode file on both Access Points:

- a. To upload a PMode XML file, connect to the administration console using your credentials (by default: login = **admin**; password = **123456**) to <http://localhost:8080/domibus>:



Figure 9 - Login to the administration console

- b. Click on the **PMode menu**, then on **Current** and finally on the **Upload** button:

The screenshot shows the "PMode - Current" update screen. On the left is a sidebar with navigation links: Messages, Message Filter, Error Log, PMode (with Current selected), Archive, Parties, JMS Monitoring, Truststore, Users, Plugin Users, Audit, Alerts, and Test Service. The main content area displays the XML code of the PMode configuration. At the bottom are buttons for Cancel, Save, Upload (highlighted in blue), and Download.

```
<?xml version="1.0" encoding="UTF-8"?>
<db:configuration xmlns:db="http://domibus.eu/configuration" party="bris_ecp_01_acc_gw">

    <mpcs>
        <mpc name="defaultMpc"
            qualifiedName="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultMPC"
            enabled="true"
            default="true"
            retention_downloaded="0"
            retention_undownloaded="14400"/>
    </mpcs>
    <businessProcesses>
        <roles>
            <role name="defaultInitiatorRole"
                value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/initiator"/>
            <role name="defaultResponderRole"
                value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/responder"/>
        </roles>
        <parties>
            <partyIdTypes>
                <partyIdType name="partyTypeUrn" value="urn:oasis:names:tc:ebcore:party:id-type:unregistered"/>
            </partyIdTypes>
            <party name="red_gw"
                endpoint="http://edelload3.westeurope.cloudapp.azure.com:7002/domibus/services/msh"
                allowChunking="false">
                <identifier partyId="domibus-red" partyIdType="partyTypeUrn"/>
            </party>
            <party name="bris_ecp_01_acc_gw"
                endpoint="http://edelload3.westeurope.cloudapp.azure.com:7001/domibus/services/msh"
                allowChunking="false">
                <identifier partyId="bris_ecp_01_acc_gw" partyIdType="partyTypeUrn"/>
            </party>
        </parties>
        <mpes>
            <mp name="oneway" value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/oneway"/>
            <mp name="twoway" value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/twoWay"/>
            <binding name="push" value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/push"/>
            <binding name="pushAndPush" value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/push-and-push"/>
        </mpes>
        <properties>
            <property name="originalSenderProperty"/>
        </properties>
    </db:configuration>
```

Figure 10 - PMode update

- c. A popup window appears where you can **select** the PMode file: select it and click on the **Upload** button. When the operation is successful you will get the following window:




Figure 11 - PMode upload success

Remark:

- Every time a PMode is updated, the Truststore is also refreshed from the file system.

Now your Tomcat Access Points are running and ready to send or receive messages.

TESTING

As explained in the Release Notes document, and to facilitate testing, we have developed a Reference Web Service endpoint to illustrate how participants can connect and interact with the AS4 Access Point to send messages.

In addition, it is possible for the backends to download received messages from their Access Point using a request (`downloadMessage`) defined in the same WSDL (check the 'Interface Control Document' for the Default WS Plugin in the Single Web Portal for more details on the WSDL¹).

Please refer to the [Test Guide](#) for more detail regarding the Testing with a SoapUI Project.

Default plugins

Domibus provides three default plugins for sending and receiving/downloading messages via Domibus, a Web Service plugin, a JMS plugin and a File System plugin.

The Web Service plugin is deployed by default with the tomcat-full distribution.

The Default JMS plugin is provided in a different archive, **domibus-distribution-X.Y.Z-default-jms-plugin.zip** including the binaries (**domibus-default-jms-plugin-X.Y.Z.jar**) and the configuration file **jms-business-defaults.properties**.

| Name | Size |
|--------|--------|
| config | 19 954 |
| lib | 20 798 |

To use the JMS plugin copy the configuration file mentioned above (**jms-business-defaults.properties**) to **<CEF-eDelivery path>/domibus/conf/domibus/plugins/config** and the plugin jar file (**domibus-default-jms-plugin-X.Y.Z.jar**) to **<CEF-eDelivery path>/domibus/conf/domibus/plugins/lib**.

An additional step is required to define filters for routing the messages towards each plugin.

Open Administration Console using your credentials (by default: login = **admin**; password = **123456**) to <http://localhost:8080/domibus> and go to the **MessageFilter** page. Use Move Up and Move Down to move the preferred plugin to the top and press Save.

¹ <https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus>

ANNEX 1: PARAMETERS

| Parameters | Local Access Point (Gateway "blue") | Remote Access Point (Gateway "red") |
|--------------------|--|---|
| Hostname | <blue_hostname>:8080 | <red_hostname>:8080 |
| Database | MySQL database | MySQL database |
| Administrator Page | Username: admin Password: 123456 http://localhost:8080/domibus | Username: admin Password: 123456 http://localhost:8080/domibus |
| Database Schema | edelivery | edelivery |
| Database connector | Username: edelivery Password: edelivery jdbc:mysql://localhost:3306/domibus* | Username: edelivery Password: edelivery jdbc:mysql://localhost:3306/domibus |
| DB username/passwd | edelivery/edelivery | edelivery/edelivery |
| PModes XML files | pmodes/domibus-gw-sample-pmode-blue.xml | pmodes/domibus-gw-sample-pmode-red.xml |

* *localhost* represents the server name that hosts the database and the application server for their respective Access Point.

ANNEX 2: FIREWALL SETTINGS

The firewall settings may prevent you from exchanging messages between your local and remote Tomcat Access Points.


To test the status of a port, run the command `telnet <server_ip> <port>`

Tomcat uses the following ports, make sure those are opened on both machines "blue" and "red" (TCP protocol):


- 8080 (HTTP port)
- 3306 (MySQL port)

This is how you can open a port on the Windows Firewall:


1. Click on **Start** then on **Control Panel**
2. Go to **Windows Firewall** and click on **Advanced Settings**
3. Right-click on **Inbound Rules** and select **New Rule...**




4. Select Port and click on Next:




5. Enter a specific local port (e.g. 8080) and click on Next:



6. Click on **Next**:



7. Choose a name for the new rule and click on **Finish** to end:



ANNEX 3: PROCESSING MODE

Processing modes (PModes) describe how messages are exchanged between AS4 partners (*Access Point blue* and *Access Point red*). These files contain the identifiers of each AS4 Access Point (identified as *parties* in the PMode file below).

Sender Identifier and Receiver Identifier represent the organizations that send and receive the business documents (respectively "**domibus-blue**" and "**domibus-red**"). They are both used in the authorization process (PMode). Therefore, adding, modifying or deleting a participant implies modifying the corresponding PMode files.

Here is an example of the content of a PMode XML file:

Remark:

In this setup we have allowed each party (blue_gw or red_gw) to initiate the process. If only blue_gw is supposed to send messages, we need to put only blue_gw in <initiatorParties> and red_gw in <responderParties>.

```
<?xml version="1.0" encoding="UTF-8"?>
<db:configuration xmlns:db="http://domibus.eu/configuration" party="blue_gw">

    <mpcs>
        <mpc name="defaultMpc"
            qualifiedName="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/defaultMPC"
            enabled="true"
            default="true"
            retention_downloaded="0"
            retention_undownloaded="14400"/>
    </mpcs>
    <businessProcesses>
        <roles>
            <role name="defaultInitiatorRole"
                value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/initiator"/>
            <role name="defaultResponderRole"
                value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/responder"/>
        </roles>
        <parties>
            <partyIdTypes>
                <partyIdType name="partyTypeUrn"
value="urn:oasis:names:tc:ebcore:partyid-type:unregistered"/>
            </partyIdTypes>
            <party name="red_gw"
                endpoint="http://<red_hostname>:8080/domibus/services/msh">
                <identifier partyId="domibus-red" partyIdType="partyTypeUrn"/>
            </party>
            <party name="blue_gw"
```

```

        endpoint="http://<blue_hostname>:8080/domibus/services/msh"
            <identifier partyId="domibus-blue" partyIdType="partyTypeUrn"/>
                </party>
            </parties>
            <meps>
                <mep name="oneway" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/oneway"/>
                <mep name="twoway" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/twoWay"/>
                <binding name="push" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/push"/>
                <binding name="pushAndPush" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/push-and-push"/>
            </meps>
            <properties>
                <property name="originalSenderProperty"
                    key="originalSender"
                    datatype="string"
                    required="true"/>
                <property name="finalRecipientProperty"
                    key="finalRecipient"
                    datatype="string"
                    required="true"/>
                <propertySet name="eDeliveryPropertySet">
                    <propertyRef property="finalRecipientProperty"/>
                    <propertyRef property="originalSenderProperty"/>
                </propertySet>
            </properties>
            <payloadProfiles>
                <payload name="businessContentPayload"
                    cid="cid:message"
                    required="true"
                    mimeType="text/xml"/>
                <payload name="businessContentAttachment"
                    cid="cid:attachment"
                    required="false"
                    mimeType="application/octet-stream"/>
                <payloadProfile name="MessageProfile" maxSize="40894464"><!-- maxSize is
currently ignored -->
                    <attachment name="businessContentPayload"/>
                    <attachment name="businessContentAttachment"/>
                </payloadProfile>
            </payloadProfiles>
            <securities>
                <security name="eDeliveryAS4Policy"
                    policy="eDeliveryAS4Policy.xml"
                    signatureMethod="RSA_SHA256" />
            </securities>
            <errorHandlings>
                <errorHandling name="demoErrorHandling"

```

```

        errorAsResponse="true"
        businessErrorNotifyProducer="true"
        businessErrorNotifyConsumer="true"
        deliveryFailureNotifyProducer="true"/>
    
```

</errorHandlings>

<agreements>

<agreement name="agreement1" value="A1" type="T1"/>

</agreements>

<services>

<service name="testService1" value="bdx:noprocess" type="tc1"/>

<service name="testService" value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/service"/>

</services>

<actions>

<action name="tc1Action" value="TC1Leg1"/>

<action name="testAction" value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/test"/>

</actions>

<as4>

<receptionAwareness name="receptionAwareness" retry="12;4;CONSTANT"

duplicateDetection="true"/>

<reliability name="AS4Reliability" nonRepudiation="true" replyPattern="response"/>

</as4>

<legConfigurations>

<legConfiguration name="pushTestcase1tc1Action"

service="testService1"

action="tc1Action"

defaultMpc="defaultMpc"

reliability="AS4Reliability"

security="eDeliveryAS4Policy"

receptionAwareness="receptionAwareness"

propertySet="eDeliveryPropertySet"

payloadProfile="MessageProfile"

errorHandling="demoErrorHandling"

compressPayloads="true"/>

<legConfiguration name="testServiceCase"

service="testService"

action="testAction"

defaultMpc="defaultMpc"

reliability="AS4Reliability"

security="eDeliveryAS4Policy"

receptionAwareness="receptionAwareness"

propertySet="eDeliveryPropertySet"

payloadProfile="MessageProfile"

errorHandling="demoErrorHandling"

compressPayloads="true"/>

</legConfigurations>

<process name="tc1Process"

```
mep="oneway"
binding="push"
initiatorRole="defaultInitiatorRole"
responderRole="defaultResponderRole">
<initiatorParties>
    <initiatorParty name="blue_gw"/>
    <initiatorParty name="red_gw"/>
</initiatorParties>
<responderParties>
    <responderParty name="blue_gw"/>
    <responderParty name="red_gw"/>
</responderParties>
<legs>
    <leg name="pushTestcase1tc1Action"/>
    <leg name="testServiceCase"/>
</legs>
</process>
</businessProcesses>
</db:configuration>
```

ANNEX 4: DOMIBUS PCONF TO EBMS3 PMODE MAPPING

The following table provides additional information concerning the Domibus PMode configuration (pconf) files.

| Domibus pconf | EbMS3 Specification [ebMS3CORE] [AS4-Profile] | Description |
|------------------------------|---|--|
| MPCs | - | Container which defines the different MPCs (Message Partition Channels). |
| MPC | PMode[1].BusinessInfo.MPC: The value of this parameter is the identifier of the MPC (Message Partition Channel) to which the message is assigned. It maps to the attribute Messaging / UserMessage | <p>Message Partition Channel allows the partition of the flow of messages from a <i>Sending MSH</i> to a <i>Receiving MSH</i> into several flows, each of which is controlled separately. An MPC also allows merging flows from several <i>Sending MSHs</i> into a unique flow that will be treated as such by a <i>Receiving MSH</i>.</p> <p>The value of this parameter is the identifier of the MPC to which the message is assigned.</p> |
| MessageRetentionDownloaded | - | Retention interval for messages already delivered to the backend. |
| MessageRetentionUnDownloaded | - | Retention interval for messages not yet delivered to the backend. |
| Parties | - | Container which defines the different PartyIdTypes, Party and Endpoint. |
| PartyIdTypes | maps to the attribute Messaging/UserMessage/PartyInfo | Message Unit bundling happens when the Messaging element contains multiple child elements or Units (either User Message Units or Signal Message Units). |
| Party ID | maps to the element Messaging/UserMessage/PartyInfo | The ebCore Party ID type can simply be used as an identifier format and therefore as a convention for values to be used in configuration and – as such – does not require any specific solution building block. |

| | | |
|--|--|--|
| Endpoint | maps to PMode[1].Protocol.Address | The endpoint is a party attribute that contains the link to the MSH. The value of this parameter represents the address (endpoint URL) of the <i>Receiver MSH</i> (or <i>Receiver Party</i>) to which Messages under this PMode leg are to be sent. Note that a URL generally determines the transport protocol (e.g. if the endpoint is an email address, then the transport protocol must be SMTP; if the address scheme is "http", then the transport protocol must be HTTP). |
| AS4 | - | Container |
| Reliability [@Nonrepudiation] [@ReplyPattern] | Nonrepudiation maps to PMode[1].Security.SendReceipt.NonRepudiation ReplyPattern maps to PMode[1].Security.SendReceipt.ReplyPattern | PMode[1].Security.SendReceipt.NoRepudiation : value = 'true' (to be used for non-repudiation of receipt), value = 'false' (to be used simply for reception awareness). PMode[1].Security.SendReceipt.ReplyPattern: value = 'Response' (sending receipts on the HTTP response or back-channel). PMode[1].Security.SendReceipt.ReplyPattern: value = 'Callback' (sending receipts use a separate connection.) |
| ReceptionAwareness [@retryTimeout] [@retryCount] [@strategy] [@duplicateDetection] | retryTimeout maps to PMode[1].ReceptionAwareness.Retry=true PMode[1].ReceptionAwareness.Retry.Parameters retryCount maps to PMode[1].ReceptionAwareness.Retry.Parameters strategy maps to PMode[1].ReceptionAwareness.Retry.Parameters duplicateDetection maps to PMode[1].ReceptionAwareness.DuplicateDetection | These parameters are stored in a composite string. <ul style="list-style-type: none">• <i>retryTimeout</i> defines timeout in seconds.• <i>retryCount</i> is the total number of retries.• <i>strategy</i> defines the frequency of retries. The only <i>strategy</i> available as of now is <i>CONSTANT</i>.• <i>duplicateDetection</i> allows to check duplicates when receiving twice the same message. The only <i>duplicateDetection</i> available as of now is <i>TRUE</i>. |
| Securities | - | Container |
| Security | - | Container |

| | | |
|------------------------------|--|---|
| Policy | PMode[1].Security.* NOT including PMode[1].Security.X509.Signature.Algorithm | The parameter in the pconf file defines the name of a WS-SecurityPolicy file. |
| SignatureMethod | PMode[1].Security.X509.Signature.Algorithm | This parameter is not supported by WS-SecurityPolicy and therefore it is defined separately. |
| BusinessProcessConfiguration | - | Container |
| Agreements | maps to eb:Messaging/ UserMessage/ CollaborationInfo/ AgreementRef | This OPTIONAL element occurs zero times or once. The <i>AgreementRef</i> element is a string that identifies the entity or artifact governing the exchange of messages between the parties. |
| Actions | - | Container |
| Action | maps to Messaging/ UserMessage/ CollaborationInfo/ Action | This REQUIRED element occurs once. The element is a string identifying an operation or an activity within a Service that may support several of these |
| Services | - | Container |
| ServiceTypes Type | maps to Messaging/ UserMessage/ CollaborationInfo/ Service[@type] | This REQUIRED element occurs once. It is a string identifying the service that acts on the message and it is specified by the designer of the service. |
| MEP [@Legs] | - | An ebMS MEP defines a typical choreography of ebMS User Messages which are all related through the use of the referencing feature (RefToMessageId). Each message of an MEP Access Point refers to a previous message of the same Access Point, unless it is the first one to occur. Messages are associated with a label (e.g. <i>request, reply</i>) that precisely identifies their direction between the parties involved and their role in the choreography. |
| Bindings | - | Container |

| | | |
|-----------------|---|---|
| Binding | - | The previous definition of ebMS MEP is quite abstract and ignores any binding consideration to the transport protocol. This is intentional, so that application level MEPs can be mapped to ebMS MEPs independently from the transport protocol to be used. |
| Roles | - | Container |
| Role | <p>maps to PMode.Initiator.Role or PMode.Responder.Role depending on where this is used. In ebMS3 message this defines the content of the following element:</p> <ul style="list-style-type: none"> • For Initiator: Messaging/UserMessage/PartyInfo/From/Role • For Responder: Messaging/UserMessage/PartyInfo/To/Role | <p>The required role element occurs once, and identifies the authorized role (<i>fromAuthorizedRole</i> or <i>toAuthorizedRole</i>) of the Party sending the message (when present as a child of the <i>From</i> element), or receiving the message (when present as a child of the <i>To</i> element). The value of the role element is a non-empty string, with a default value of http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultRole</p> <p>Other possible values are subject to partner agreement.</p> |
| Processes | - | Container |
| PayloadProfiles | - | Container |
| Payloads | - | Container |


| | | |
|----------------------------|--|--|
| Payload | maps to PMode[1].BusinessInfo.PayloadProfile | <p>This parameter allows specifying some constraint or profile on the payload. It specifies a list of payload parts.</p> <p>A payload part is a data structure that consists of five properties:</p> <ol style="list-style-type: none"> 1. name (or Content-ID) that is the part identifier, and can be used as an index in the notation PayloadProfile; 2. MIME data type (text/xml, application/pdf, etc.); 3. name of the applicable XML Schema file if the MIME data type is text/xml; 4. maximum size in kilobytes; 5. Boolean string indicating whether the part is expected or optional, within the User message. <p>The message payload(s) must match this profile.</p> |
| ErrorHandlings | - | Container |
| ErrorHandling | - | Container |
| ErrorAsResponse | maps to PMode[1].ErrorHandling.Report.AsResponse | This Boolean parameter indicates (if <i>true</i>) that errors generated from receiving a message in error are sent over the back-channel of the underlying protocol associated with the message in error. If <i>false</i> , such errors are not sent over the back-channel. |
| ProcessErrorNotifyProducer | maps to PMode[1].ErrorHandling.Report.ProcessErrorNotifyProducer | This Boolean parameter indicates whether (if <i>true</i>) the Producer (application/party) of a User Message matching this PMode should be notified when an error occurs in the Sending MSH, during processing of the <i>User Message to be sent</i> . |

| | | |
|-------------------------------|--|---|
| ProcessErrorNotifyConsumer | maps to PMode[1].ErrorHandling.Report.ProcessErrorNotifyProducer | This Boolean parameter indicates whether (if <i>true</i>) the Consumer (application/party) of a User Message matching this PMode should be notified when an error occurs in the Receiving MSH, during processing of the <i>received User message</i> . |
| DeliveryFailureNotifyProducer | maps to PMode[1].ErrorHandling.Report.DeliveryFailuresNotifyProducer | When sending a message with this reliability requirement (<i>Submit</i> invocation), one of the two following outcomes shall occur: - The Receiving MSH successfully delivers (<i>Deliver</i> invocation) the message to the Consumer. - The Sending MSH notifies (<i>Notify</i> invocation) the Producer of a delivery failure. |
| Legs | - | Container |
| Leg | - | Because messages in the same MEP may be subject to different requirements - e.g. the reliability, security and error reporting of a response may not be the same as for a request – the PMode will be divided into <i>legs</i> . Each user message label in an ebMS MEP is associated with a PMode leg. Each PMode leg has a full set of parameters for the six categories above (except for <i>General Parameters</i>), even though in many cases parameters will have the same value across the MEP legs. Signal messages that implement transport channel bindings (such as <i>PullRequest</i>) are also controlled by the same categories of parameters, except for <i>BusinessInfo group</i> . |
| Process | - | In <i>Process</i> everything is plugged together. |

Domibus pconf to ebMS3 mapping

ANNEX 5: INTRODUCTION TO AS4 SECURITY

To secure the exchanges between Access Points "blue" and "red" (*Access Point "blue"* is sending a message to *Access Point "red"* in this example), it is necessary to set up each Access Point's *keystore* and *truststore* accordingly. The diagram below shows a brief explanation of the main steps of this process:



In order to exchange B2B messages and documents between *Access Points* blue and red, it is necessary to check the following:

| For blue | For red |
|---|--|
| Check that <i>red_gw</i> certificate (public key of red) is in gateway_truststore.jks of blue. If it is not, add it. | Check that <i>blue_gw</i> certificate (public key of blue) is in gateway_truststore.jks of red. If it is not, add it. |
| Check that the <i>blue_gw</i> private key is in the gateway_keystore.jks. If it is not, add it. | Check that <i>red_gw</i> private key is in the gateway_keystore.jks. If it is not, add it. |
| In <i>domibus.properties</i> : the keystore alias should be <i>blue_gw</i> , you may edit the keystore password (by default <i>test123</i>), and the path to gateway_keystore.jks and gateway_truststore.jks (if you change it). | In <i>domibus.properties</i> : the alias property should be <i>red_gw</i> , you can edit the keystore password (by default <i>test123</i>), and the path to gateway_keystore.jks and gateway_truststore.jks (if you change it). |

In a production environment, each participant would need a certificate delivered by a certification authority and remote exchanges between business partners would be managed by each partner's PMode (that should be uploaded on each Access Point).

Remark:

It is necessary to open the required ports when Access Point blue or Access Point red is behind a local firewall. For instance, the port 8080 is not opened by default in Windows. Therefore we would need to create a dedicated rule on Windows firewall to open the TCP 8080 port. See also the Annex "[Firewall Settings](#)".

CONTACT INFORMATION

CEF Support Team

By email: CEF-EDELIVERY-SUPPORT@ec.europa.eu

SUPPORT Service: 8am to 6pm (Normal EC working Days)