



EUROPEAN COMMISSION

DIGIT
Connecting Europe Facility

Access Point

Administration Guide

Domibus 4.0-RC1

Version [1.7]

Status [Final]

© European Union, 2018

Reuse of this document is authorised provided the source is acknowledged. The Commission's reuse policy is implemented by Commission Decision 2011/833/EU of 12 December 2011 on the reuse of Commission documents.

Date: 07/08/2018

Document Approver(s):

| Approver Name | Role |
|---------------|----------------------|
| Adrien FERIAL | CEF Technical Office |
| | |
| | |

Document Reviewers:

| Reviewer Name | Role |
|------------------------|----------------------|
| Cosmin BACIU | CEF Technical Office |
| Catalin-Emanuel ENACHE | CEF Technical Office |
| | |

Summary of Changes:

| Version | Date | Created by | Short Description of Changes |
|---------|------------|-------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1.07 | 09/02/2018 | Chaouki BERRAH Caroline AEBY | Update for version 3.3.2 Information on MySQL and Oracle deletion scripts added as well as Domibus operational guidelines. |
| 1.08 | 20/03/2018 | Caroline AEBY | Reuse notice added, links to AS4 specifications updated. |
| 1.09 | 04/04/2018 | Chaouki BERRAH Caroline AEBY | Domibus 3.3.3 |
| 1.2 | 16/04/2018 | Caroline AEBY | Domibus 3.3.4 PMode configuration moved from plugin management section into separate section. Domibus properties: dynamic.discovery => dynamicdiscovery. 2 new properties added: domibus.dynamicdiscovery.partyid.responder.role & domibus.dynamicdiscovery.partyid.type |
| 1.3 | 21/06/2018 | Chaouki BERRAH | Domibus 3.3.4 Updates + binary files sources references updated |
| 1.4 | 01/07/2018 | CEF Support | Updates for Domibus 4.0. Section on Plugin notification added. |
| 1.5 | 26/07/2018 | Chaouki BERRAH Ioana DRAGUSANU Cosmin BACIU Tiago MIGUEL Thomas DUSSART | Update PMODE MultiTenancy Test Service and domibus.properties Alerts Section added |
| 1.6 | 31/07/2018 | Cosmin BACIU CEF Support Thomas DUSSART | Updates |
| 1.7 | 01/08/2018 | Catalin-Emanuel ENACHE | Information on WildFly 12 added |

Table of Contents

| | |
|-----------------------------------------------------|-----------|
| 1. INTRODUCTION | 7 |
| 1.1. Purpose..... | 7 |
| 1.2. References..... | 7 |
| 2. CONVENTIONS..... | 9 |
| 2.1. Example 1: Sample Oracle Statement..... | 9 |
| 2.2. Example 2: Sample Configuration file | 9 |
| 3. PREREQUISITES..... | 10 |
| 3.1. Binaries repository | 10 |
| 4. DOMIBUS DEPLOYMENT | 11 |
| 4.1. Database Configuration..... | 11 |
| 4.1.1. MySQL and Oracle Deletion scripts | 11 |
| 4.1.2. MySQL configuration | 11 |
| 4.1.3. Oracle configuration..... | 13 |
| 4.2. Domibus on WebLogic 12.1.3..... | 13 |
| 4.2.1. Single Server Deployment | 13 |
| 4.2.2. Clustered Deployment..... | 23 |
| 4.3. Domibus on Tomcat | 34 |
| 4.3.1. Pre-Configured Single Server Deployment..... | 34 |
| 4.3.2. Single Server Deployment | 37 |
| 4.3.3. Clustered Deployment..... | 39 |
| 4.4. Domibus on WildFly | 40 |
| 4.4.1. Pre-Configured Single Server Deployment..... | 40 |
| 4.4.2. Single Server Deployment | 45 |
| 4.4.3. Clustered Deployment..... | 51 |
| 5. DOMIBUS CONFIGURATION | 55 |
| 5.1. Security Configuration..... | 55 |
| 5.1.1. Security Policies..... | 55 |
| 5.1.2. Certificates..... | 56 |
| 5.2. Domibus Properties..... | 57 |
| 6. PLUGIN MANAGEMENT | 64 |
| 6.1. Default Plugins..... | 64 |
| 6.1.1. JMS Plugin..... | 64 |
| 6.1.2. WS Plugin..... | 64 |
| 6.1.2.1. Domibus authentication..... | 64 |
| 6.1.2.2. Domibus Authorization | 65 |
| 6.1.2.3. Enable the authentication in Domibus..... | 65 |
| 6.1.3. File System Plugin..... | 65 |

| | |
|--------------------------------------------------------------------|------------|
| 6.2. Custom Plugin..... | 66 |
| 6.2.1. Plugin registration | 66 |
| 6.2.1.1. Tomcat..... | 66 |
| 6.2.1.2. WebLogic | 66 |
| 6.2.1.3. WildFly..... | 66 |
| 6.3. Plugin notifications..... | 67 |
| 7. PMODE CONFIGURATION..... | 68 |
| 7.1. Configuration..... | 68 |
| 7.1.1. Adding a new participant | 68 |
| 7.1.2. Sample PMode file | 69 |
| 7.1.3. Domibus PMode configuration to ebMS3 PMode Mapping | 72 |
| 7.1.4. Upload new Configuration | 77 |
| 7.1.4.1. Upload the PMode file | 77 |
| 7.1.4.2. Upload the Truststore | 80 |
| 8. SPECIAL SCENARIO: SENDER AND RECEIVER ARE THE SAME | 82 |
| 8.1. PMode Configuration | 82 |
| 8.2. Message structure | 82 |
| 8.3. Message ID convention | 83 |
| 9. ADMINISTRATION TOOLS..... | 84 |
| 9.1. Administration Console | 84 |
| 9.1.1. Changing passwords..... | 84 |
| 9.1.2. User Account Lockout Policy | 86 |
| 9.1.3. Adding new users | 88 |
| 9.1.4. Message Filtering | 89 |
| 9.2. Message Log | 92 |
| 9.3. Application Logging | 93 |
| 9.3.1. Domibus log files | 93 |
| 9.3.2. Logging properties..... | 93 |
| 9.3.3. Error Log page | 94 |
| 9.4. Queue Monitoring..... | 94 |
| 9.5. Configuration of the queues..... | 102 |
| 9.5.1. Tomcat..... | 102 |
| 9.5.2. WebLogic | 103 |
| 9.5.3. WildFly..... | 103 |
| 10. LARGE FILES SUPPORT..... | 104 |
| 11. DATA ARCHIVING..... | 105 |
| 11.1. What's archiving? | 105 |
| 11.2. Data Retention Policy | 105 |
| 11.3. Data Extraction | 105 |

| | |
|----------------------------------------------------------------------------------------|------------|
| 12. NON REPUDIATION | 107 |
| 13. TLS CONFIGURATION | 108 |
| 13.1. TLS Configuration | 108 |
| 13.1.1. Transport Layer Security in Domibus | 108 |
| 13.1.2. Client side configuration (One Way SSL) | 108 |
| 13.1.3. Client side configuration (Two Way SSL) | 109 |
| 13.1.4. Server side configuration | 109 |
| 13.1.4.1. Tomcat 8 | 109 |
| 13.1.4.2. WebLogic | 110 |
| 13.1.4.3. WildFly 9 | 110 |
| 13.1.4.4. Configure Basic and Certificates authentication in SoapUI..... | 111 |
| 13.1.4.5. PMode update..... | 112 |
| 14. DYNAMIC DISCOVERY OF UNKNOWN PARTICIPANTS | 114 |
| 14.1. Overview..... | 114 |
| 14.2. Domibus configuration for PEPPOL..... | 114 |
| 14.3. PMode configuration for PEPPOL..... | 115 |
| 14.3.1. Sender PMode | 115 |
| 14.3.2. Receiver PMode | 116 |
| 14.4. Policy and certificates for PEPPOL..... | 116 |
| 14.5. Exception sending context initialized event to listener instance of class | 117 |
| 14.6. Neither the JAVA_HOME nor the JRE_HOME environment variable is defined | 117 |
| 14.7. Cannot access Admin Console..... | 118 |
| 14.8. Handshake Failure | 118 |
| 14.9. Message format for PEPPOL..... | 120 |
| 14.10. SMP entry | 122 |
| 14.11. Domibus configuration for OASIS..... | 122 |
| 14.12. PMode configuration for OASIS | 122 |
| 14.12.1. Sender PMode | 122 |
| 14.12.2. Receiver PMode | 124 |
| 14.13. Policy and certificates for OASIS | 124 |
| 14.14. Exception sending context initialized event to listener instance of class | 125 |
| 14.15. Neither the JAVA_HOME nor the JRE_HOME environment variable is defined | 125 |
| 14.16. Cannot access Admin Console..... | 125 |
| 14.17. Handshake Failure | 126 |
| 14.18. Message format for OASIS | 128 |
| 15. MESSAGE PULLING..... | 129 |
| 15.1. Setup..... | 129 |
| 15.2. Configuration restriction | 129 |
| 16. MULTI-TENANCY..... | 131 |
| 16.1. Configuration..... | 131 |

| | |
|---------------------------------------------------------------------------------------|------------|
| 16.1.1. Tomcat Configuration..... | 131 |
| 16.1.2. WebLogic and WildFly Configuration..... | 132 |
| 16.2. Domain Properties..... | 132 |
| 16.3. Logging | 134 |
| 16.4. Plugins | 135 |
| 16.5. Users..... | 135 |
| 17. TEST SERVICE | 136 |
| 17.1. Test Service Configuration..... | 136 |
| 18. ALERT FEATURE | 138 |
| 18.1. Description | 138 |
| 18.2. Main configuration | 138 |
| 18.3. Message status change alerts | 140 |
| 18.4. Authentication Alerts | 141 |
| 18.5. Certificate scanner alerts..... | 142 |
| 19. OPERATIONAL GUIDELINES | 144 |
| 19.1. JMS Queue Management..... | 144 |
| 19.2. Log Management..... | 144 |
| 19.2.1. Log Level | 144 |
| 19.2.2. Log Rotation and Archiving | 145 |
| 19.2.3. Log Monitoring | 145 |
| 19.3. Capacity Planning | 145 |
| 19.3.1. JVM Memory Management..... | 145 |
| 19.3.2. CPU, IO operations and Disk Space Monitoring | 145 |
| 19.4. Database Management | 145 |
| 19.4.1. Database Monitoring..... | 145 |
| 19.4.2. Database Archiving..... | 145 |
| 19.4.3. Monitor Message Life Cycle | 145 |
| 20. TROUBLESHOOTING..... | 148 |
| 20.1. Failed to obtain DB connection from datasource | 148 |
| 20.2. Exception sending context initialized event to listener instance of class | 149 |
| 20.3. Neither the JAVA_HOME nor the JRE_HOME environment variable is defined | 149 |
| 20.4. Cannot access Admin Console..... | 149 |
| 20.5. Handshake Failure | 150 |
| 21. ANNEX 1 - USAGE OF CERTIFICATES IN PEPPOL AND OASIS..... | 153 |
| 22. ANNEX 2 – DOCUMENT PARTS | 154 |
| 23. LIST OF FIGURES..... | 155 |
| 24. CONTACT INFORMATION | 156 |

1. INTRODUCTION

This Administration Guide is intended for Server Administrators in charge of installing, managing and troubleshooting an eDelivery Access Point.

1.1. Purpose

The purpose of this guide is to provide detailed information on how to deploy and configure Domibus on WebLogic, Tomcat and WildFly with MySQL or Oracle. It also provides detailed descriptions of related Security Configurations (Policies, Certificates), Message Filtering, PMode Configuration, Application Monitoring, Custom Plugins Registration, JMS Monitoring, Data Archiving, Troubleshooting and TLS Configuration.

1.2. References

| Ref. | Document | Content outline |
|--------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------|
| [REF1] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus | Location of the release artefacts on the CEF Digital site |
| [REF2] | https://dev.mysql.com/downloads/connector/j/ | Location to download the MySQL JDBC driver from the Official website |
| [REF3] | http://www.oracle.com/technetwork/database/features/jdbc/default-2280470.html | Location of the Oracle JDBC driver from the Official website |
| [REF4] | https://docs.jboss.org/author/display/WFLY9/WildFly+9+Cluster+Howto | Location to the Official documentation on how to setup a cluster on WildFly 9 |
| [REF5] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/PKI+Service | CEF Public Key Infrastructure (PKI) Service Offering Document |
| [REF6] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus | Location of the latest Domibus release on the Single Web Portal |

| Ref. | Document | Content outline |
|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------|
| [REF7] | https://access.redhat.com/documentation/en-US/Red_Hat_JBoss_Fuse/6.0/html/XML_Configuration_Reference/files/cxf-http-conf-2_7_0_xsd_Element_http-conf_tlsClientParameters.html | RedHat page for the XML Configuration Reference of the <i>http-conf:tlsClientParameters</i> element |
| [REF8] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/eDelivery+SMP | SMP (Service Metadata Publisher) and Dynamic Discovery in AS4 Gateways |
| [REF9] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/eDelivery+SMP | Space describing the SMP (Service Metadata Publisher) |
| [REF10] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/eDelivery+AS4 | eDelivery AS4 Profile |
| [REF11] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus | Software Architecture Document (SAD) |
| [REF12] | https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus | JMS Plugin Interface Control Document (ICD) |

2. CONVENTIONS

The commands and configuration files listed in this document usually contain a mix of reserved words (commands, instructions and system related special words) and user defined words (chosen by the user) as well as comments and preferred values for certain variables. The conventions used in this document, to distinguish between them, are the followings:

- To keep this document release agnostic as much as possible, the strings "x-y-z" or "x.y.z" are intended to refer to the version of Domibus discussed in this version of the document, in the present case "Domibus 4.0-RC1".
- **Bold** is used for "reserved" words and commands.
- *Normal italic* together with a short description of the argument is used for user-defined names (chosen by you to designate items like users, passwords, database etc.). Normally contains at least 2 words separated by "_".
- ***Bold and Italic*** is used for advisable values which can be changed by the user depending on their infrastructure.
- Comments are sometimes added to describe the purpose of the commands, usually enclosed in brackets () .

By default, non-OS specific paths will be described using Linux patterns.

2.1. Example 1: Sample Oracle Statement

```
create user edelivery_user identified by edelivery_password;
```

```
grant all privileges to edelivery_user;
```

(Where *edelivery_user* and *edelivery_password* are names chosen by the user)

2.2. Example 2: Sample Configuration file

```
jdbc.datasource.0.driver.name=com.mysql.jdbc.Driver
```

```
jdbc.datasource.0.driver.url=jdbc:mysql://localhost:3306/domibus_schema
```

```
jdbc.datasource.0.driver.password=edelivery_password
```

```
jdbc.datasource.0.driver.username=edelivery_user
```

(Where:

- *edelivery_user*, *domibus_schema* and *edelivery_password* are names chosen by the user.

- ***localhost:3306*** represents hostname:port parameters of the MySQL database.)

3. PREREQUISITES

Please install the following software on the target system. For further information and installation details, we kindly advise you to refer to the software owner's documentation.

- Java runtime environment (JRE), version 8:
<http://www.oracle.com/technetwork/java/javase/downloads/index.html>
- One of the supported Database Management Systems :
 - MySQL 5,6 or above
 - Oracle 10g+
- If you don't plan to deploy Domibus according to the Pre-Configured Single Server Deployment method, you must also install one of the supported application/web servers:
 - WebLogic 12c
 - WildFly 9 or WildFly 12
 - Apache Tomcat 8.0.x
- All Domibus installation resources, including full distributions and documentation can be found on the Single Web Portal :
<https://ec.europa.eu/cefdigital/wiki/display/CEFDIGITAL/Domibus>

3.1. Binaries repository

All the Domibus 4.0-RC1 artefacts can be directly downloaded from the CEF Digital site (cf.[REF1]).

4. DOMIBUS DEPLOYMENT

Remark:

The variable **cef_edelivery_path** referring to the folder where the package is installed will be used later in this document.

4.1. Database Configuration

For this step, you will have to use the following resources (see section §3.1—"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-sql-scripts.zip**

4.1.1. MySQL and Oracle Deletion scripts

A deletion script for MySQL and Oracle Domibus DB is available in the **domibus-distribution-X.Y.Z-sql-scripts.zip**.

The purpose of the script is to delete all messages within a user defined period to recover disk space. The script requires a START_DATE parameter and an END_DATE parameter to be set.

The tables affected by the execution of this script are:

- TB_MESSAGING
- TB_ERROR_LOG
- TB_PARTY_ID
- TB_RECEIPT_DATA
- TB_PROPERTY
- TB_PART_INFO
- TB_RAWENVELOPE_LOG
- TB_ERROR
- TB_USER_MESSAGE
- TB_SIGNAL_MESSAGE
- TB_RECEIPT
- TB_MESSAGE_INFO
- TB_MESSAGE_LOG

Any information relevant to a message received or sent during the predefined period, will be removed from these tables.

In order to execute this script, it is advised to use a UI tool such as SQL developer of MySQL workbench.

Important: in order to keep the JMS queues synchronized with the DB data that will be deleted by this script, the Domibus Administrator should remove manually the associated JMS messages from the plugin notifications queues

4.1.2. MySQL configuration

1. Unzip **domibus-distribution-X.Y.Z-sql-scripts.zip** in **cef_edelivery_path/sql-scripts**.

2. Open a command prompt and navigate to this directory: `cef_edelivery_path/sql-scripts`.
3. (Optional) Storing payload messages in a database with size over 30 MB.

Domibus can temporarily store the messages in the database.

Therefore, it is required to increase the maximum allowed size of packets. Update the default properties of **my.ini** (Windows) or **my.cnf** (Linux).


- **max_allowed_packet** property

```
# The maximum size of one packet or any generated or intermediate string, or any
# parameter sent by the
# mysql_stmt_send_long_data() C API function.
max_allowed_packet=512M
```

- **innodb_log_file_size** property

```
# Size of each log file in a log group. You should set the combined size
# of log files to about 25%-100% of your buffer pool size to avoid
# unneeded buffer pool flush activity on log file overwrite. However,# note that larger logfile size
will increase the time needed for the recovery process
innodb_log_file_size=5120M
```

- Restart MySQL service (Windows):



The screenshot shows the Windows Services window with the following details:

| Service Name | Type | Status | Dependencies |
|-------------------------|------------|---------|--------------|
| MSSQLServerADHelper 100 | SQL Server | Stopped | N/A |
| MySQL56 | MySQL | Running | N/A |
| napagent | Network | Stopped | NetworkSe... |

MySQL service

4. (Optional) For storing payload messages in a file system instead of a database see §5.2 – "[Domibus Properties](#)".
5. For MySQL 8 and Connector/J 8.0.x please set the database timezone. One way of setting the timezone is to modify the MySQL **my.ini** configuration file by adding the following property with the adjusted timezone. It is recommended that the database timezone is the same as the timezone of the machine where Domibus is installed.

```
default-time-zone='+00:00'
```

6. Execute the following MySQL commands at the command prompt :

Remark:

User defined names like root_password, domibus_schema etc..., are in italic as described in the Convention section.

```
mysql -h localhost -u root_user --password=root_password -e "drop schema if exists
domibus_schema;create schema domibus_schema;alter database domibus_schema charset=utf8
collate=utf8_bin; create user edelivery_user@localhost identified by 'edelivery_password';grant all
on domibus_schema.* to edelivery_user@localhost;"
```

The above creates a schema (*domibus_schema*) and a user (*edelivery_user*) that have all the privileges on the schema.

```
mysql -h localhost -u root_user --password=root_password domibus_schema < mysql5innodb-x.y.z.ddl
```

The above creates the required tables in *domibus_schema*.

Remark:

If you are using Windows, make sure to have the parent directory of mysql.exe added to your PATH variable.

4.1.3. Oracle configuration

1. Unzip **domibus-distribution-X.Y.Z-sql-scripts.zip** in *cef_edelivery_path/sql-scripts*
2. Open a command prompt and navigate to this directory: *cef_edelivery_path/sql-scripts*.
3. Open a command line session, log in and execute the following commands :

```
sqlplus sys as sysdba (password should be the one assigned during the Oracle installation )
```

=====

Once logged in Oracle:

```
create user edelivery_user identified by edelivery_password;
grant all privileges to edelivery_user;
grant execute on dbms_xa to edelivery_user;
grant select on pending_trans$ to edelivery_user;
grant select on dba_2pc_pending to edelivery_user;
grant select on dba_pending_transactions to edelivery_user;
connect edelivery_user
show user; (should return : edelivery_user)
@oracle10g-x.y.z.ddl (run the scripts with the @ sign from the location of the scripts)
exit
```

4.2. Domibus on WebLogic 12.1.3

This section does not include the installation of WebLogic server 12.1.3. It is assumed that the WebLogic Server is installed and a Domain is created.

Hereafter the domain location will be referred as *DOMAIN_HOME* (*user defined name*).

4.2.1. Single Server Deployment

For this step, you will have to use the following resources (see section §3.1—"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-weblogic-war.zip**
- **domibus-distribution-X.Y.Z-weblogic-configuration.zip**
- **domibus-distribution-X.Y.Z-default-ws-plugin.zip** (optional)
- **domibus-distribution-X.Y.Z-default-jms-plugin.zip** (optional)
- **domibus-distribution-X.Y.Z-default-fs-plugin.zip** (optional)

1. Download and unzip **domibus-distribution- X.Y.Z-weblogic-configuration.zip** in the directory **DOMAIN_HOME/conf/domibus**

| Name | Size |
|--------------------|---------|
| internal | 9 895 |
| plugins | 113 252 |
| policies | 17 634 |
| domibus.properties | 6 318 |
| logback.xml | 5 121 |

2. Download and unzip **domibus-distribution- X.Y.Z-weblogic-war.zip** in a temporary folder to prepare it for deployment.
3. Configure your Keystore based on section §5.1.2 – *"Certificates"*
4. Add the following lines in:
 - o **For Windows : DOMAIN_HOME\bin\setDomainEnv.cmd**
 - Locate the **set DOMAIN_HOME** statement and add the following lines after:

```
...
set DOMAIN_HOME
# Added for Domibus *****
set EXTRA_JAVA_PROPERTIES=%EXTRA_JAVA_PROPERTIES% -
Ddomibus.config.location=%DOMAIN_HOME%/conf/domibus
# *****
...
```
 - o **For Linux : DOMAIN_HOME/bin/setDomainEnv.sh**
 - Locate the **export DOMAIN_HOME** statement and add the following lines after:

```
...
export DOMAIN_HOME
# Added for Domibus *****
EXTRA_JAVA_PROPERTIES="$EXTRA_JAVA_PROPERTIES -Ddomibus.config.location=$DOMAIN_HOME/conf/domibus"
export EXTRA_JAVA_PROPERTIES
# *****
...
```

5. Run the WebLogic Scripting Tool (WLST) in order to create the JMS resources and the Database datasources from the command line:

- o Download the WLST Package from following location:
<https://ec.europa.eu/cefdigital/artifact/content/repositories/eDelivery/eu/europa/ec/digit/pcis/wslt-api/1.9.1/wslt-api-1.9.1.zip>
- o Configure the WSLT API tool
 - Unzip the **wslt-api-1.9.1.zip**

- Define the **WL_HOME** as a system environment variable to point to the WebLogic 'wlserver' directory as defined in the **DOMAIN_HOME/bin/setDomainEnv.[cmd|sh]**
e.g. `WL_HOME=/wls12130/wlserver`
- Take the script **WeblogicSingleServer.properties** from **domibus-distribution-X.Y.Z-weblogic-configuration.zip** under the scripts directory and copy the **WeblogicSingleServer.properties** file into the **wslt-api-1.9.1** directory and adapt the following properties :
 - Adapt the properties for connecting to the WebLogic domain:

```
domain.loading.type=connect
domain.connect.url=t3://localhost:7001
domain.connect.username=weblogic_name
domain.connect.password=weblogic_password
domain.name=my_domain1
```

- Adapt the `jdbc.datasource` properties for the datasources:

- For Oracle database:

```
jdbc.datasource.0.name=eDeliveryDs
jdbc.datasource.0.driver.name=oracle.jdbc.xa.client.OracleXADataSource
jdbc.datasource.0.driver.url=jdbc:oracle:thin:@127.0.0.1:1521:xe
jdbc.datasource.0.driver.password=edelivery_password
jdbc.datasource.0.driver.username=edelivery_username

jdbc.datasource.1.name=eDeliveryNonXA
jdbc.datasource.1.driver.name= oracle.jdbc.OracleDriver
jdbc.datasource.1.driver.url=jdbc:oracle:thin:@127.0.0.1:1521:xe
jdbc.datasource.1.driver.password=edelivery_password
jdbc.datasource.1.driver.username=edelivery_username
```

Remark:

MySQL configuration is commented by default. To enable MySQL, remove the comment (#) from the lines below. Don't forget to add the comment (#) for Oracle to disable it.

- For MySQL:

```
jdbc.datasource.0.driver.name=com.mysql.jdbc.Driver
# Connector/J 8.0.x
#jdbc.datasource.0.driver.name= com.mysql.cj.jdbc.Driver
jdbc.datasource.0.driver.url=jdbc:mysql://localhost:3306/domibus_schema
jdbc.datasource.0.driver.password=edelivery_password
jdbc.datasource.0.driver.username=edelivery_username
jdbc.datasource.0.transaction.protocol=LoggingLastResource
jdbc.datasource.0.pool.connection.test.onreserv.sql=SQL SELECT 1

jdbc.datasource.1.driver.name=com.mysql.jdbc.Driver
# Connector/J 8.0.x
#jdbc.datasource.1.driver.name= com.mysql.cj.jdbc.Driver
jdbc.datasource.1.driver.url=jdbc:mysql://localhost:3306/domibus_schema
jdbc.datasource.1.driver.password=edelivery_password
jdbc.datasource.1.driver.username=edelivery_username
```

```

jdbc.datasource.1.transaction.protocol=None
jdbc.datasource.1.pool.connection.test.onreserv.sql=SQL SELECT 1

#.
#.
#.

#Oracle
#domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=oracle.jdbc.xa
.client.OracleXADataSource
#domibus.entityManagerFactory.jpaProperty.hibernate.dialect=org.hibernate.dialect.Oracle10
gDialect
#MySQL
domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=com.mysql.jdbc
.Driver
# Connector/J 8.0.x
#domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=
com.mysql.cj.jdbc.Driver
domibus.entityManagerFactory.jpaProperty.hibernate.dialect=org.hibernate.dialect.MySQL5In
noDBDialect

```

- Adapt the property for location of the filestore
persistent.filestore.0.location.

Example:

```
persistent.filestore.0.location=DOMAIN_HOME/filestore
```

Remark:

Make sure that the path for the filestore contains forward slashes (/).

- Adapt if necessary the JMX security configuration:

Example:

```

#####
## Policy configuration
#####
security.policies.0.mode = CREATE
security.policies.0.resource = type=<jmx>, operation=invoke, application=,
mbeanType=weblogic.management.runtime.JMSDestinationRuntimeMBean
security.policies.0.realm = myrealm
security.policies.0.authorizer = XACMLAuthorizer
security.policies.0.expression= Rol(Admin) | Grp(Administrators) | Grp(JMSManagers)
security.policies.items = 1
#####
## Users configuration
#####
security.users.0.realm=myrealm
security.users.0.name=jmsManager
security.users.0.password=jms_Manager1
security.users.0.comment=
security.users.0.authenticator=DefaultAuthenticator
security.users.items=1
#####
## Groups configuration
#####
security.groups.0.realm=myrealm
security.groups.0.name=JMSManagers
security.groups.0.description=

```

```

security.groups.0.authenticator=DefaultAuthenticator
security.groups.items=1
#####
## Groups Membership configuration
#####
security.group.member.0.user=jmsManager
security.group.member.0.groups=JMSManagers
security.group.member.0.realm=myrealm
security.group.member.0.authenticator=DefaultAuthenticator
security.group.member.items=1

```

- Start the WebLogic domain from within *DOMAIN_HOME*:
 - For Windows:
startWebLogic.cmd
 - For Linux:
startWebLogic.sh
- Execute the following command from within the **wlstapi-1.9.1/bin** directory:
 - For Windows:
wlstapi.cmd ..\scripts\import.py --property ..\WeblogicSingleServer.properties
 - For Linux:
wlstapi.sh .../scripts/import.py --property ..//WeblogicSingleServer.properties

Expected result:

```

Saving all your changes ...
Saved all your changes successfully.
Activating all your changes, this may take a while ...
The edit lock associated with this edit session is released
once the activation is completed.
Activation completed
Location changed to serverRuntime tree. This is a read-only tree with DomainMBean as the root.
For more help, use help('domainConfig')

Disconnected from weblogic server: AdminServer

```

6. Activate the use of the authorization providers to protect the JMX access:

Home >Summary of Security Realms >**myrealm**

Messages

All changes have been activated. However 1 items must be restarted for the changes to take effect.

Settings for myrealm

Configuration Users and Groups Roles and Policies Credential Mappings Providers Migration

General RDBMS Security Store User Lockout Performance

Click the **Lock & Edit** button in the Change Center to modify the settings on this page.

Name: myrealm

Security Model Default: DD Only

Combined Role Mapping Enabled

Use Authorization Providers to Protect JMX Access

Advanced

Save

Click the **Lock & Edit** button in the Change Center to modify the settings on this page.

- The database dialect is pre-configured to use the Oracle database. If you are using a MySQL database, you should adapt the following properties in **<DOMAIN_HOME>/conf/domibus/domibus.properties** as highlighted in the example below:

```
# ----- EntityManagerFactory -----
domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=
com.mysql.jdbc.jdbc2.optional.MysqlXADataSource
domibus.entityManagerFactory.jpaProperty.hibernate.dialect=org.hibernate.dialect.MySQL5InnoDBDialect
```

- Install the WS Plugin. For more details, see section §6.2.1.2 – [WebLogic](#).


- Deploy **domibus-distribution-X.Y.Z-weblogic.war**
 - Click on **Install**:

This screenshot shows the Oracle WebLogic Server Administration Console 12c interface. The left sidebar displays the 'Domain Structure' for 'mydomain3' under the 'Deployments' section. The main content area is titled 'Summary of Deployments' and contains two tables. The first table has columns: Name, State, Health, Type, Targets, and Deployment Order. The second table also has columns: Name, State, Health, Type, Targets, and Deployment Order. Both tables have 'Install', 'Update', and 'Delete' buttons at the top. The 'Install' button in the first table is highlighted with a red box.


- Navigate to the location of the .war file and click **Next**:

This screenshot shows the 'Install Application Assistant' page. The left sidebar is identical to the previous screenshot. The main content area is titled 'Install Application Assistant'. It includes a 'Messages' section with a green checkmark indicating the file was uploaded successfully. Below it is a 'Locate deployment to install and prepare for deployment' section. A note states: 'Select the file path that represents the application root directory, archive file, exploded archive directory, or application module descriptor that you want to install. You can also enter the path of the application directory or file in the Path field.' A note below it says: 'Note: Only valid file paths are displayed below. If you cannot find your deployment files, upload your file(s) and/or confirm that your application contains the required deployment descriptors.' The 'Path:' field contains the path 'C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload\domibus-distribut'. The 'Recently Used Paths:' field shows 'C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload'. The 'Current Location:' field shows 'localhost \ C: \ wls12130 \ user_projects \ domains \ mydomain3 \ servers \ AdminServer \ upload'. A radio button is selected next to the file 'domibus-distribution-x.y.z-weblogic.war'. At the bottom, there are 'Back', 'Next', 'Finish', and 'Cancel' buttons, with the 'Next' button highlighted with a red box.

- Choose **Install this deployment as an application** and click **Next**:



- Accept the default options and click **Next**:



- Select the following option and click **Finish**:

ORACLE® WebLogic Server Administration Console 12c

Change Center

View changes and restarts

Configuration editing is enabled. Future changes will automatically be activated as you modify, add or delete items in this domain.

Domain Structure

- mydomain3
 - + Environment
 - Deployments
 - + Services
 - Security Realms
 - + Interoperability
 - + Diagnostics

How do I...

- Start and stop a deployed enterprise application
- Configure an enterprise application
- Create a deployment plan
- Target an enterprise application to a server
- Test the modules in an enterprise application

System Status

Health of Running Servers

| |
|----------------|
| Failed (0) |
| Critical (0) |
| Overloaded (0) |
| Warning (0) |

Install Application Assistant

Review your choices and click **Finish**

Click **Finish** to complete the deployment. This may take a few moments to complete.

Additional configuration

In order to work successfully, this application may require additional configuration. Do you want to review this application's configuration after completing this assistant?

Yes, take me to the deployment's configuration screen.

No, I will review the configuration later.

Summary

Deployment: C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload\domibus-distribution-x.y.z-weblogic.war

Name: domibus-distribution-x.y.z-weblogic

Staging Mode: Use the defaults defined by the chosen targets

Plan Staging Mode: Use the same accessibility as the application

Security Model: DDOOnly: Use only roles and policies that are defined in the deployment descriptors.

Target Summary

| Components | Targets |
|-------------------------------------|-------------|
| domibus-distribution-x.y.z-weblogic | AdminServer |

Back **Next** **Finish** **Cancel**

- Here is an overview of the resulting settings, you can now click on the **Save** button:

The screenshot shows the Oracle WebLogic Server Administration Console interface. On the left, there's a sidebar titled 'Change Center' with 'View changes and restarts' and a note about configuration editing. Below it is the 'Domain Structure' tree, which includes 'mydomain3' with nodes like Environment, Deployments, Services, Security Realms, Interoperability, and Diagnostics. To the right, the main content area displays the 'Settings for domibus-distribution-x.y.z-weblogic' page under the 'Overview' tab. The 'Save' button is highlighted with a red box. The page lists deployment details: Name (domibus-distribution-x.y.z-weblogic), Context Root (/domibus-weblogic), Path (C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload\domibus-distribution-x.y.z-weblogic.war), Deployment Plan (no plan specified), Staging Mode (not specified), and Plan Staging Mode (not specified). A note at the bottom states: 'Specifies whether a deployment plan's files are copied from a source on the Administration Server to the Managed Server's staging area during application preparation.' A 'How do I...' panel on the left provides links for deploying web applications, configuring them, creating deployment plans, testing deployments, and monitoring web applications and servlets.

The expected positive response to the deployment request should be the following:

The screenshot shows the 'Messages' section of the Oracle WebLogic Server Administration Console. It displays two green checkmarks with the text: 'All changes have been activated. No restarts are necessary.' and 'Settings updated successfully.'


10. Verify the installation by navigating with your browser to <http://localhost:7001/domibus-weblogic>: if you can access the page it means the deployment was successful.

(By default: User = **admin**; Password = **123456**)

Remark:

It is recommended to change the passwords for the default users (See §9.1 – "Administration" for further information).

Expected result:



4.2.2. Clustered Deployment




Figure 1 - Diagram representing the Deployment of Domibus in a Cluster on WebLogic

Remark:

In this section, we assume that a Domain and a WebLogic Cluster are already setup.

For this step, you will have to use the following resources (see section §3.1–“Binaries repository” for the download location):

- **domibus-distribution-X.Y.Z-weblogic-war.zip**
- **domibus-distribution-X.Y.Z-weblogic-configuration.zip**
- **domibus-distribution-X.Y.Z-default-ws-plugin.zip** (optional)
- **domibus-distribution-X.Y.Z-default-jms-plugin.zip** (optional)
- **domibus-distribution-X.Y.Z-default-fs-plugin.zip** (optional)

1. Download and unzip **domibus-distribution- X.Y.Z-weblogic-configuration.zip** in a shared location that is accessible by all the nodes from the cluster. We will refer to this directory as **cef_shared_edelivery_path/Domibus**.
2. Download and unzip **domibus-distribution- X.Y.Z-weblogic-war.zip** in a temporary folder to prepare it for deployment.
3. Configure your Keystore based on section §5.1.2 – “Certificates”
4. Add the following lines in:

- For Windows : DOMAIN_HOME\bin\setDomainEnv.cmd

- Locate the **set DOMAIN_HOME** statement and add the following lines after:

```
...
set DOMAIN_HOME
# Added for Domibus ****
set EXTRA_JAVA_PROPERTIES=%EXTRA_JAVA_PROPERTIES% -
Ddomibus.config.location=%DOMAIN_HOME%/conf/domibus
# ****
...
```

- For Linux : DOMAIN_HOME/bin/setDomainEnv.sh

- Locate the **export DOMAIN_HOME** statement and add the following lines after:

```
...
export DOMAIN_HOME
# Added for Domibus ****
EXTRA_JAVA_PROPERTIES="$EXTRA_JAVA_PROPERTIES -Ddomibus.config.location=$DOMAIN_HOME/conf/domibus"
export EXTRA_JAVA_PROPERTIES
# ****
...
```

5. Run the WebLogic Scripting Tool (WLST) in order to create the necessary JMS resources and Database datasources from the command line:

- Download the WLST Package from the following location:

<https://ec.europa.eu/cefdigital/artifact/content/repositories/eDelivery/eu/europa/ec/digit/ipcis/wslt-api/1.9.1/wslt-api-1.9.1.zip>

- Configure the WSLT API tool:
 - Unzip the **wslt-api-1.9.1.zip**
 - Define the WL_HOME (SET or export command depending on your operating system) environment variable to point to the WebLogic **wlserver** directory

e.g. WL_HOME=/wls12130/wlserver

- Take the script **WeblogicCluster.properties** from **domibus-distribution-X.Y.Z-weblogic-configuration.zip** under the scripts directory and copy the **WeblogicCluster.properties** file into the **wslt-api-1.9.1** directory and apply the following changes :
- Adapt the properties for connecting to the WebLogic domain

```
domain.loading.type=connect
domain.connect.url=t3://localhost:7001
domain.connect.username=weblogic_user
domain.connect.password=weblogic_password
domain.name=mydomain1
```

- Adapt the jdbc.datasource properties for the datasources

For Oracle database:

```
jdbc.datasource.0.name= eDeliveryDs
jdbc.datasource.0.driver.name=oracle.jdbc.xa.client.OracleXADataSource
jdbc.datasource.0.driver.url=jdbc:oracle:thin:@127.0.0.1:1521:xe
jdbc.datasource.0.driver.password=edelivery_password
jdbc.datasource.0.driver.username=edelivery_username
jdbc.datasource.0.targets=cluster_name

jdbc.datasource.1.name=edeliveryNonXA
jdbc.datasource.1.driver.name= oracle.jdbc.OracleDriver
jdbc.datasource.1.driver.url=jdbc:oracle:thin:@127.0.0.1:1521:xe
jdbc.datasource.1.driver.password=edelivery_password
jdbc.datasource.1.driver.username=edelivery_username
jdbc.datasource.1.targets=cluster_name
```

For MySQL database:

Remark:

MySQL configuration is commented by default. To enable MySQL, remove the comment (#) from the lines below. Don't forget to add the comment (#) for Oracle to disable it.

```
jdbc.datasource.0.name= eDeliveryDs
jdbc.datasource.0.driver.name=com.mysql.jdbc.Driver
# Connector/J 8.0.x
#jdbc.datasource.0.driver.name= com.mysql.cj.jdbc.Driver
jdbc.datasource.0.driver.url=jdbc:mysql://localhost:3306/domibus_schema
jdbc.datasource.0.driver.password=edelivery_password
jdbc.datasource.0.driver.username=edelivery_username
jdbc.datasource.0.targets=cluster_name
```

```

jdbc.datasource.0.transaction.protocol=LoggingLastResource
jdbc.datasource.0.pool.connection.test.onreserv.sql=SQL SELECT 1

jdbc.datasource.1.name= edeliveryNonXA
jdbc.datasource.1.driver.name=com.mysql.jdbc.Driver
# Connector/J 8.0.x
#jdbc.datasource.1.driver.name= com.mysql.cj.jdbc.Driver
jdbc.datasource.1.driver.url=jdbc:mysql://localhost:3306/domibus_schema
jdbc.datasource.1.driver.password=edelivery_password
jdbc.datasource.1.driver.username=edelivery_username
jdbc.datasource.1.targets=cluster_name
jdbc.datasource.1.transaction.protocol=None
jdbc.datasource.1.pool.connection.test.onreserv.sql=SQL SELECT 1

```

- Adapt the properties for target and location of the filestore:

```

persistent.filestore.0.target=cluster_name
persistent.filestore.0.location=DOMAIN_HOME/filestores

```

Remark:

If you are using Windows, make sure that the paths for the filestore contain forward slash (/).

- Adapt if necessary the JMX security configuration:

Example:

```

#####
## Policy configuration
#####
security.policies.0.mode = CREATE
security.policies.0.resource = type=<jmx>, operation=invoke, application=,
mbeanType=weblogic.management.runtime.JMSDestinationRuntimeMBean
security.policies.0.realm = myrealm
security.policies.0.authorizer = XACMLAuthorizer
security.policies.0.expression= Rol(Admin)/Grp/Administrators)/Grp(JMSManagers)
security.policies.items = 1
#####
## Users configuration
#####
security.users.0.realm=myrealm
security.users.0.name=jmsManager
security.users.0.password=jms_Manager1
security.users.0.comment=
security.users.0.authenticator=DefaultAuthenticator
security.users.items=1
#####
## Groups configuration
#####
security.groups.0.realm=myrealm
security.groups.0.name=JMSManagers
security.groups.0.description=
security.groups.0.authenticator=DefaultAuthenticator
security.groups.items=1
#####
## Groups Membership configuration
#####

```

```
security.group.member.0.user=jmsManager
security.group.member.0.groups=JMSManagers
security.group.member.0.realm=myrealm
security.group.member.0.authenticator=DefaultAuthenticator
security.group.member.items=1
```

- Adapt the property for JMS Server:

Example:

```
jms.server.0.target=cluster_name
```

- Adapt the property for JMS Module:

Example:

```
jms.module.0.targets=cluster_name
```

- Start the WebLogic domain from within *DOMAIN_HOME*:

- For Windows:

```
startWebLogic.cmd
```

- For Linux:

```
startWebLogic.sh
```

- Execute the following command from within the **wlstapi-1.9.1/bin** directory:

For Windows:

```
wlstapi.cmd ..\scripts\import.py --
property ..\WeblogicCluster.properties
```

For Linux:

```
wlstapi.sh ..\scripts\import.py --
property ..\WeblogicCluster.properties
```

Expected result:

```
Saving all your changes ...
Saved all your changes successfully.
Activating all your changes, this may take a while ...
The edit lock associated with this edit session is released
once the activation is completed.
Activation completed
Location changed to serverRuntime tree. This is a read-only tree with DomainMBean as the root.
For more help, use help('domainConfig')

Disconnected from weblogic server: AdminServer
```

6. Activate the use of the authorization providers to protect the JMX access:

The screenshot shows the 'Settings for myrealm' page in the Oracle WebLogic Administration Console. The 'General' tab is active. A note at the top states: 'All changes have been activated. However 1 items must be restarted for the changes to take effect.' Below this, there are tabs for Configuration, Users and Groups, Roles and Policies, Credential Mappings, Providers, and Migration. A note says: 'Click the Lock & Edit button in the Change Center to modify the settings on this page.' A 'Save' button is present. The 'Name:' field is set to 'myrealm'. Under 'Security Model Default', it is set to 'DD Only'. There is a checked checkbox for 'Combined Role Mapping Enabled'. The 'Use Authorization Providers to Protect JMX Access' checkbox is checked and highlighted with a red rectangle. An 'Advanced' link is visible below it. A note at the bottom says: 'Click the Lock & Edit button in the Change Center to modify the settings on this page.'

7. The database dialect is pre-configured to use the Oracle database. If you are using the MySQL database you should adapt the dialect as highlighted in the text below in `<DOMAIN_HOME>/conf/domibus/domibus.properties` file :

```
#EntityManagerFactory
domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=
com.mysql.jdbc.jdbc2.optional.MysqlXADataSource
domibus.entityManagerFactory.jpaProperty.hibernate.dialect=org.hibernate.dialect.MySQL5InnoDBDialect
```

8. Install the WS plugin. For more details, refer to chapter §6.2.1.2 – "WebLogic".

9. Deploy **domibus-distribution-X.Y.Z-weblogic.war**.


- Click **Install**

The screenshot shows the Oracle WebLogic Server Administration Console 12c. The left sidebar shows a 'Domain Structure' tree with 'mydomain3' expanded, showing 'Environment', 'Deployments' (which is selected), 'Services', 'Security Realms', 'Interoperability', and 'Diagnostics'. The main panel is titled 'Summary of Deployments' under the 'Control' tab. It displays a table with columns: Name, State, Health, Type, Targets, and Deployment Order. A message at the bottom states 'There are no items to display'. Below the table, there are 'Install', 'Update', 'Delete', 'Start', and 'Stop' buttons. A red box highlights the 'Install' button in the top toolbar and the 'Install' button in the table footer.


- Navigate to location **DOMAIN_HOME/conf/domibus** where the **domibus-distribution-X.Y.Z-weblogic.war** file has been previously copied.
- Select the **domibus-distribution-X.Y.Z-weblogic.war** file and click **Next**:

The screenshot shows the Oracle WebLogic Server Administration Console 12c. The left sidebar shows a 'Domain Structure' tree with 'mydomain3' expanded. The right panel is titled 'Install Application Assistant'. It has 'Back', 'Next', 'Finish', and 'Cancel' buttons. A message in the center says 'The file domibus-distribution-x.y.z-weblogic.war has been uploaded successfully to C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload'. Below it, a 'Locate deployment to install and prepare for deployment' section asks to select the file path. A note says 'Only valid file paths are displayed below. If you cannot find your deployment files, upload your file(s) and/or confirm that your application contains the required deployment descriptors.' The 'Path:' field shows 'C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload\domibus-distrib'. The 'Recently Used Paths:' dropdown shows 'C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload'. The 'Current Location:' dropdown shows 'localhost \ C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload' with 'domibus-distribution-x.y.z-weblogic.war' selected. A red box highlights the 'Next' button in the dialog footer.

- Choose **Install this deployment as an application** and click **Next**:



- Select your cluster for the deployment target and click **Next**:



- Select the following options and click **Next**:

The screenshot shows the Oracle WebLogic Server Administration Console 12c interface. On the left, there's a sidebar with 'Change Center' and 'View changes and restarts' sections. Below that is the 'Domain Structure' tree, which includes 'mydomain3' with its sub-nodes: Environment, Deployments, Services, Security Realms, Interoperability, and Diagnostics. To the right of the sidebar is the main content area titled 'Install Application Assistant'. At the top of this area are buttons: Back, Next (which is highlighted with a red box), Finish, and Cancel. Below these buttons is a section titled 'Optional Settings' with the sub-section 'General'. Under 'General', there's a question 'What do you want to name this deployment?' followed by a text input field containing the value 'domibus-distribution-x.y.z-weblogic'. There are also sections for 'Security' and 'Source Accessibility'. Under 'Source Accessibility', the option 'Use the defaults defined by the deployment's targets' is selected. At the bottom of the 'Source Accessibility' section, there's a 'Location' field containing the path 'C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer'. At the very bottom of the page, there's a note: 'Provide the location from where all targets will access this application's files. This is often a shared directory. You must ensure the'. The bottom right corner of the screenshot area has a small watermark: 'www.wso2.com'.

- Select the following option and click **Finish**:

ORACLE® WebLogic Server Administration Console 12c

Change Center

View changes and restarts

Configuration editing is enabled. Future changes will automatically be activated as you modify, add or delete items in this domain.

Domain Structure

mydomain3

- + Environment
- + Deployments
- + Services
- + Security Realms
- + Interoperability
- + Diagnostics

How do I...

- Start and stop a deployed enterprise application
- Configure an enterprise application
- Create a deployment plan
- Target an enterprise application to a server
- Test the modules in an enterprise application

System Status

Health of Running Servers

| |
|----------------|
| Failed (0) |
| Critical (0) |
| Overloaded (0) |
| Warning (0) |

Install Application Assistant

Review your choices and click **Finish**

Click **Finish** to complete the deployment. This may take a few moments to complete.

Additional configuration

In order to work successfully, this application may require additional configuration. Do you want to review this application's configuration after completing this assistant?

Yes, take me to the deployment's configuration screen.

No, I will review the configuration later.

Summary

Deployment: C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload\domibus-distribution-x.y.z-weblogic.war

Name: domibus-distribution-x.y.z-weblogic

Staging Mode: Use the defaults defined by the chosen targets

Plan Staging Mode: Use the same accessibility as the application

Security Model: DDOOnly: Use only roles and policies that are defined in the deployment descriptors.

Target Summary

| Components | Targets |
|-------------------------------------|-------------|
| domibus-distribution-x.y.z-weblogic | AdminServer |

Back **Next** **Finish** **Cancel**

- Here is an overview of the resulting settings, you can now click on the **Save** button:

ORACLE® WebLogic Server Administration Console 12c

Change Center

View changes and restarts

Configuration editing is enabled. Future changes will automatically be activated as you modify, add or delete items in this domain.

Domain Structure

mydomain3

- + Environment
- + Deployments
- + Services
- + Security Realms
- + Interoperability
- + Diagnostics

How do I...

- Deploy Web applications
- Configure Web applications
- Create a deployment plan
- Test the deployment
- Monitor Web applications and servlets

Settings for domibus-distribution-x.y.z-weblogic

Overview Deployment Plan Configuration Security Targets Control Testing Monitoring Notes

Save

Use this page to view the installed configuration of a Web application.

| | |
|-----------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Name: domibus-distribution-x.y.z-weblogic | The name of this application deployment. More Info... |
| Context Root: /domibus-weblogic | The specific path at which this Web application is found by a servlet. More Info... |
| Path: C:\wls12130\user_projects\domains\mydomain3\servers\AdminServer\upload\domibus-distribution-x.y.z-weblogic.war | The path to the source of the deployable unit on the Administration Server. More Info... |
| Deployment Plan: (no plan specified) | The path to the deployment plan document on the Administration Server. More Info... |
| Staging Mode: (not specified) | Specifies whether an application's files are copied from a source on the Administration Server to the Managed Server's staging area during application preparation. More Info... |
| Plan Staging Mode: (not specified) | Specifies whether a deployment plan's files are copied from a source on the Administration Server to the Managed Server's staging area during application preparation. More Info... |

The expected positive response to the deployment request should be the following:

The screenshot shows a browser window with the Domibus Administration Console. The top navigation bar includes links for Home, Log Out, Preferences, Record, and Help. A search bar is also present. The main content area displays a breadcrumb path: Home > Summary of Deployments > domibus-distribution-x.y.z-weblogic. Below this, a section titled "Messages" contains two green checkmark notifications: "All changes have been activated. No restarts are necessary." and "Settings updated successfully."

10. Verify the installation by navigating with your browser to <http://localhost:7001/domibus-weblogic>

If you can access the page it means the deployment was successful.

(by default: user = **admin**; password = **123456**)

Remark:

It is recommended to change the passwords for the default users (See §9.1 – "Administration" for further information).

Expected result:

The screenshot shows the login interface of the Domibus Administration Console. On the left is a sidebar with icons and labels for Messages, Message Filter, Error Log, PMode, JMS Monitoring, and Truststore. The main right panel contains a login form with fields for "Username *" (set to "admin") and "Password *". The password field contains five dots. A yellow "Login" button is at the bottom of the form.

4.3. Domibus on Tomcat

Remark:

As Tomcat is not a full Java EE application server and does not offer JMS capabilities by default, Domibus uses ActiveMQ as an in-memory JMS broker when deployed on a Tomcat servlet container. The configuration for the ActiveMQ JMS broker can be found in `cef_edelivery_path/domibus/internal/activemq.xml`.

4.3.1. Pre-Configured Single Server Deployment

For this step, you will have to use the following resources (see section §3.1—"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-tomcat-full.zip**

1. Unzip the archive:

- Unzip **domibus-distribution-X.Y.Z-tomcat-full.zip** to a location on your physical machine: `cef_edelivery_path`.

| Name | Size |
|------------------|------------|
| domibus | 66 739 870 |
| sql-scripts | 70 415 |
| changelog.txt | 3 045 |
| upgrade-info.txt | 6 600 |

2. Prepare the database:

- For MySQL database:

Add MySQL JDBC driver (available on MySQL official web site cf. [REF2]) in the folder `cef_edelivery_path/domibus/lib`.

Remark:

The version of the JDBC driver has to be `mysql-connector-java-5.1.40.jar` or higher.

Edit the properties file `cef_edelivery_path/conf/domibus/domibus.properties` and adjust the highlighted parts in the text below according to your environment. The properties associated to the database configuration are pre-configured for the MySQL database:

```
# ----- Database -----
#Database server name
domibus.database.serverName=localhost

#Database port
domibus.database.port=3306

#XA properties
domibus.datasource.xa.property.user=edelivery_user
domibus.datasource.xa.property.password=edelivery_password
#MySQL
domibus.datasource.xa.property.url=jdbc:mysql://${domibus.database.serverName}:${domibus.database.port}/ domibus_schema?pinGlobalTxToPhysicalConnection=true
```

```
#Non-XA Datasource
domibus.datasource.url=jdbc:mysql://${domibus.database.serverName}:${domibus.database.port}/domibus_schema?useSSL=false
domibus.datasource.user=edelivery_user
domibus.datasource.password=edelivery_password
```

- For Oracle database:

Add the Oracle JDBC driver (e.g. **ojdbc7.jar**) (available on the Oracle official web site cf.[REF3]) in the **cef_edelivery_path/domibus/lib** folder.

Edit the properties file **cef_edelivery_path/conf/domibus/domibus.properties** and adjust the highlighted parts in the text below according to your environment:

```
# ----- Database -----
#Database server name
domibus.database.serverName=localhost

#Database port
domibus.database.port=1521

#XA Datasource
domibus.datasource.xa.xaDataSourceClassName=oracle.jdbc.xa.client.OracleXADatasource
#XA properties
domibus.datasource.xa.property.user=edelivery_user
domibus.datasource.xa.property.password=edelivery_password
domibus.datasource.xa.property.url=jdbc:oracle:thin:@${domibus.database.serverName}:${domibus.database.port}[:SID//Service]

#Non-XA Datasource
domibus.datasource.driverClassName=oracle.jdbc.OracleDriver
domibus.datasource.URL=jdbc:oracle:thin:@${domibus.database.serverName}:${domibus.database.port}[:SID//Service]
domibus.datasource.user=edelivery_user
domibus.datasource.password=edelivery_password
```

Remark:

Configure the database dialect as it is pre-configured for MySQL by default.

```
#EntityManagerFactory
domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=oracle.jdbc.xa.client.OracleXADatasource
domibus.entityManagerFactory.jpaProperty.hibernate.dialect=org.hibernate.dialect.Oracle10gDialect
```

3. Configure your Keystore based on section §5.1.2 – ["Certificates"](#).
4. Set JVM parameters:

Domibus expects a single environment variable **domibus.config.location**, pointing towards the **cef_edelivery_path/conf/domibus** folder.

You can do this by editing the first command lines of **cef_edelivery_path\domibus\bin\setenv.bat** (Windows) or **cef_edelivery_path/domibus/bin/setenv.sh** (Linux). Set **CATALINA_HOME** equal to the absolute path of the installation **cef_edelivery_path/domibus**.

- For Windows : edit `cef_edelivery_path\domibus\bin\setenv.bat` by adding the following:

```
...
set CATALINA_HOME=cef_edelivery_path\domibus
set JAVA_OPTS=%JAVA_OPTS% -Dfile.encoding=UTF-8 -Xms128m -Xmx1024m -XX:PermSize=64m
set JAVA_OPTS=%JAVA_OPTS% -Ddomibus.config.location=%CATALINA_HOME%\conf\domibus
...
```

- For Linux : edit `cef_edelivery_path/domibus/bin/setenv.sh` by adding the following:

```
...
export CATALINA_HOME=cef_edelivery_path/domibus
export JAVA_OPTS="$JAVA_OPTS -Xms128m -Xmx1024m "
export JAVA_OPTS="$JAVA_OPTS -Ddomibus.config.location=$CATALINA_HOME/conf/domibus"
...
```

5. Launch the Domibus application:

- For Windows :

```
cd cef_edelivery_path\domibus\bin\
startup.bat
```

- For Linux :


```
cd cef_edelivery_path /domibus/bin/chmod u+x *.sh ./startup.sh
```

6. Display the Domibus home page on your browser: <http://localhost:8080/domibus>.
(By default: User = **admin**; Password = **123456**)

Remark:

It is recommended to change the passwords for the default users. See §9.1 – "Administration" for further information.

If you can access the page it means the deployment was successful.

Expected result:**4.3.2. Single Server Deployment**

For this step, you will have to use the following resources (see §3.1 – [Binaries repository](#) for the download location):

- **domibus-distribution-X.Y.Z-tomcat-configuration.zip**
- **domibus-distribution-X.Y.Z-tomcat-war.zip**

We assume that an Apache Tomcat 8.0.x is already installed and the installation location is now considered as your *cef_edelivery_path/domibus*.

1. Download and unzip the artefact **domibus-distribution-X.Y.Z-tomcat-configuration.zip** into the directory *cef_edelivery_path/conf/domibus*.
2. Configure the MySQL or Oracle datasource as indicated in §4.3.1 – "Pre-Configured Single Server Deployment"
3. Configure your Keystore based on §5.1.2 – "Certificates".
4. Execute step 4 from §4.3.1 – "Pre-Configured Single Server Deployment".
5. If not already present, create a folder and name it **temp** under *cef_edelivery_path/conf/Domibus*.
6. Rename **domibus-MSH-X.Y.Z-tomcat.war** to **domibus.war** and deploy it to *cef_edelivery_path/domibus /webapps*.

| Name | Size |
|-----------------------------|------------|
| domibus.war | 60 612 036 |

7. Launch the Domibus application:

- For Windows :

```
cd cef_edelivery_path\domibus\bin\
startup.bat
```

- For Linux :

```
cd cef_edelivery_path /domibus/bin/  
chmod +x *.sh  
.startup.sh
```

7. Display the Domibus home page on your browser: <http://localhost:8080/domibus>
(By default: User = **admin**; Password = **123456**):

Remark:

It is recommended to change the passwords for the default users. See §9.1 – "Administration" for further information.

If you can access the page it means the deployment was successful.

Expected result:

The screenshot shows the login interface of the Domibus Administration Console. On the left, there is a sidebar with the following menu items:

- Messages
- Message Filter
- Error Log
- PMode
- JMS Monitoring
- Truststore

The main area contains a login form with the following fields:

Username *
admin

Password *
••••••|

4.3.3. Clustered Deployment




Figure 2 - Diagram representing the Deployment of Domibus in a Cluster on Tomcat

Remark:

In this section we assume that a JMS Broker and a Loadbalancer are configured separately (e.g. `httpd`).

For this step, you will have to use the following resources (see §3.1—"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-tomcat-full.zip**
- **domibus-distribution-X.Y.Z-tomcat-war.zip**

1. Follow steps **1, 2, 3, 4** and **5** from the §4.3.2 – "[Single Server Deployment](#)"
2. Set the JVM parameters:

Domibus expects a single JVM parameter `$domibus.config.location`, pointing towards the `cef_edelivery_path/conf/domibus` folder.

You can do this by editing `cef_edelivery_path\domibus\bin\setenv.bat` (Windows) or `cef_edelivery_path/domibus/bin/setenv.sh` (Linux). Set `CATALINA_HOME` equal to the absolute path of the installation `cef_edelivery_path/Domibus`.

- For Windows: edit `cef_edelivery_path\domibus\bin\setenv.bat` by adding the following:

Remark:

`your_node_id` refers to the installed node in the cluster which starts normally at 01 (then 02, etc.).

```
...
set CATALINA_HOME=cef_edelivery_path\domibus
set JAVA_OPTS=%JAVA_OPTS% -Dfile.encoding=UTF-8 -Xms128m -Xmx1024m -XX:PermSize=64m
set JAVA_OPTS=%JAVA_OPTS% -Ddomibus.config.location=%CATALINA_HOME%\conf\domibus
set JAVA_OPTS=%JAVA_OPTS% -Ddomibus.node.id=your_node_id
...
```

- For Linux : edit `cef_edelivery_path/domibus/bin/setenv.sh` by adding the following:

```
...
export CATALINA_HOME=cef_edelivery_path/domibus
export JAVA_OPTS=$JAVA_OPTS -Xms128m -Xmx1024m
export JAVA_OPTS="$JAVA_OPTS -Ddomibus.config.location=${CATALINA_HOME}/conf/domibus"
export JAVA_OPTS="$JAVA_OPTS -Ddomibus.node.id=your_node_id"
...
```

3. Integrate the external JMS Broker with Domibus by adapting the following properties in `cef_edelivery_path/conf/domibus/domibus.properties`.
 - Please note that the `activeMQ.embedded.configurationFile` property should be deleted as the JMS broker is external.

```
#ActiveMQ
activeMQ.broker.host=localhost
activeMQ.brokerName=localhost
#activeMQ.embedded.configurationFile=file://${domibus.config.location}/internal/activemq.xml
activeMQ.connectorPort=1199
activeMQ.rmiServerPort=1200
activeMQ.transportConnector.uri=tcp://${activeMQ.broker.host}:61616
activeMQ.username=domibus
activeMQ.password=changeit
```

4. Change the following properties related to the **Atomikos** configuration in parameters in `cef_edelivery_path/conf/domibus/domibus.properties`:

For clustered deployment:

Uncomment the following lines:

```
#com.atomikos.icatch.output_dir=${domibus.work.location:${domibus.config.location}}/work/transactions
/${domibus.node.id}
#com.atomikos.icatch.log_base_dir=${domibus.work.location:${domibus.config.location}}/work/transactions
/${domibus.node.id}/log
```

Comment the following lines:

```
com.atomikos.icatch.output_dir=${domibus.work.location:${domibus.config.location}}/work/transactions
com.atomikos.icatch.log_base_dir=${domibus.work.location:${domibus.config.location}}/work/transactions
/log
```

5. Follow step **6** and **7** from the §4.3.2 – ["Single Server Deployment"](#).

4.4. Domibus on WildFly

4.4.1. [Pre-Configured Single Server Deployment](#)

In this section we assume that WildFly is installed at the location `cef_edelivery_path/domibus`.

For this step, you will have to use the following resources (see section §3.1 – ["Binaries repository"](#) for the download location):

- **domibus-distribution-X.Y.Z-wildfly-full.zip zip (WildFly 9 version)**
- **or domibus-distribution-X.Y.Z-wildfly12-full.zip (WildFly 12 version)**

Remark: below steps apply for both distributions of Domibus.

1. Download and unzip the **domibus-distribution-X.Y.Z-wildfly-full.zip** archive in your *cef_edelivery_path* location.

| Name | Size |
|------------------|-------------|
| domibus | 222 551 064 |
| sql-scripts | 70 415 |
| changelog.txt | 3 045 |
| upgrade-info.txt | 6 600 |

2. Configure the MySQL database (Option 1).

- o Drivers:

Create the directory
cef_edelivery_path/domibus/modules/system/layers/base/com/mysql/main if it does not exist.

Under this directory:

- Download the MySQL JDBC driver available on MySQL official web site (cf.[REF2]) and copy it in the folder.

Remark:

The version of the driver has to be mysql-connector-java-5.1.40.jar or higher.

- Create or edit the file
cef_edelivery_path/domibus/modules/system/layers/base/com/mysql/main/module.xml and copy the following module configuration. Make sure to put the name of the driver you are using as an argument of **resource-root** element. e.g. **mysql-connector-java-5.1.40.jar**:

```
<module xmlns="urn:jboss:module:1.3" name="com.mysql">
    <resources>
        <resource-root path="mysql-connector-java-5.1.40.jar"/>
    </resources>
    <dependencies>
        <module name="javax.api"/>
        <module name="javax.transaction.api"/>
    </dependencies>
</module>
```

- Add your DBMS driver metadata to the Drivers section of the
cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml.

```
<subsystem xmlns="urn:jboss:domain:datasources:3.0">
    .....
    <datasources>
        .....
        <drivers>
            <driver name="com.mysql" module="com.mysql">
                <driver-class>com.mysql.jdbc.Driver</driver-class>
                <xa-datasource-class>
                    com.mysql.jdbc.jdbc2.optional.MysqlXADataSource
                </xa-datasource-class>
            </driver>
        </drivers>
    </datasources>
</subsystem>
```

```

<!--Connector/J 8.0.x
<driver-class>com.mysql.cj.jdbc.Driver</driver-class>
<xa-datasource-class>com.mysql.cj.jdbc.MysqlXADataSource</xa-datasource-class>
-->
</driver>
<drivers>
.....
</datasources>
.....
</subsystem>

```

- Datasources:
 - Add the datasources as indicated below to
cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml.

Remark:

*Please make sure you modify the connection details for the **MysqlXADS** datasource for MySQL according to your environment.*

```

<subsystem xmlns="urn:jboss:domain:datasources:3.0">
<datasources>
.....
<xa-datasource jndi-name="java:/jdbc/cipaeDeliveryDs" pool-
name="eDeliveryMysqlXADS" enabled="true" use-ccm="true" statistics-enabled="true">
    <xa-datasource-property name="ServerName">localhost</xa-datasource-property>
    <xa-datasource-property name="DatabaseName">domibus_schema</xa-datasource-property>
    <xa-datasource-class>com.mysql.jdbc.jdbc2.optional.MysqlXADataSource</xa-datasource-class>
    <!--Connector/J 8.0.x
    <xa-datasource-class>com.mysql.cj.jdbc.MysqlXADataSource</xa-datasource-class>
-->

    <driver>com.mysql</driver>
    <security>
        <user-name>edelivery_user</user-name>
        <password>edelivery_password</password>
    </security>
<validation>
<valid-connection-checker class-
name="org.jboss.jca.adapters.jdbc.extensions.mysql.MySQLValidConnectionChecker"/>
<background-validation>true</background-validation>
<exception-sorter class-name="org.jboss.jca.adapters.jdbc.extensions.mysql.MySQLExceptionSorter"/>
    </validation>
</xa-datasource>
<datasource jndi-name="java:/jdbc/cipaeDeliveryNonXADS" pool-name="eDeliveryMysqlNonXADS"
enabled="true" use-ccm="true">
    <connection-url>jdbc:mysql://localhost:3306/domibus_schema</connection-url>
    <driver-class>com.mysql.jdbc.Driver</driver-class>
    <!--Connector/J 8.0.x
    <driver-class>com.mysql.cj.jdbc.Driver</driver-class>
-->
    <driver>com.mysql</driver>
    <security>
        <user-name>edelivery_username</user-name>
        <password>edelivery_password</password>
    </security>
    <validation>
        <valid-connection-checker class-
name="org.jboss.jca.adapters.jdbc.extensions.mysql.MySQLValidConnectionChecker"/>

```

```

<background-validation>true</background-validation>
<exception-sorter class-name="org.jboss.jca.adapters.jdbc.extensions.mysql.MySQLExceptionSorter"/>
</validation>
</datasource>
.....
</datasources>
</subsystem>

```

3. Configure the Oracle Database (option 2):

- Drivers:

Create the directory *cef_edelivery_path/domibus/modules/system/layers/base/com/oracle/main* if it does not exist. Under this directory:

- Download and copy the Oracle JDBC driver (e.g. *ojdbc7.jar*, available on the Oracle official web site cf.[REF3]) in the folder.
- Copy the file *cef_edelivery_path/domibus/modules/system/layers/base/com/mysql/main/module.xml* in the recently created folder.

Edit **module.xml** by copying the following module configuration. Make sure to put the name of the driver you are using as an argument of **resource-root** element. e.g. *ojdbc7.jar*:

```

<module xmlns="urn:jboss:module:1.3" name="com.oracle">
    <resources>
        <resource-root path="ojdbc7.jar"/>
    </resources>
    <dependencies>
        <module name="javax.api"/>
        <module name="javax.transaction.api"/>
    </dependencies>
</module>

```

- Add your DBMS driver metadata to the Drivers section in *cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml* (only change the items described below while replacing MYSQL configuration in the process):

```

<subsystem xmlns="urn:jboss:domain:datasources:3.0">
    <datasources>
        .....
        <xa-datasource jndi-name="java:/jdbc/cipaeDeliveryDs" pool-name="eDeliveryOracleXADS"
            enabled="true" use-ccm="true">
            <xa-datasource-property name="URL">jdbc:oracle:thin:@localhost:1521[:SID]/Service</xa-datasource-property>
            <driver>com.oracle</driver>
            <user-name>edelivery_user</user-name>
            <password>edelivery_password</password>
        </xa-datasource>
    </datasources>
</subsystem>

```

- Datasources:

- Add the datasources as indicated below to *cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml*.

Remark:

*Please make sure you modify the connection details for the **eDeliveryOracleXADS** datasource for Oracle according to your environment.*

```
<valid-connection-checker class-
name="org.jboss.jca.adapters.jdbc.extensions.oracle.OracleValidConnectionChecker"/>
    <exception-sorter class-
name="org.jboss.jca.adapters.jdbc.extensions.oracle.OracleExceptionSorter"/>

    <driver name="com.oracle" module="com.oracle">
        <xa-datasource-class>oracle.jdbc.xa.client.OracleXADataSource</xa-datasource-class>
<datasource jta="true" jndi-name="java:/jdbc/cipaeDeliveryNonXADS" pool-name="eDeliveryOracleNonXADS"
enabled="true" use-ccm="true">
    <connection-url>jdbc:oracle:thin:@localhost:1521[:SID]/Service</connection-url>
    <driver-class>oracle.jdbc.OracleDriver</driver-class>
    <driver>com.oracle</driver>
    <security>
        <user-name>edelivery_username</user-name>
        <password>edelivery_password</password>
    </security>
    <validation>
        <valid-connection-checker class-
name="org.jboss.jca.adapters.jdbc.extensions.oracle.OracleValidConnectionChecker"/>
        <background-validation>true</background-validation>
        <stale-connection-checker class-
name="org.jboss.jca.adapters.jdbc.extensions.oracle.OracleStaleConnectionChecker"/>
        <exception-sorter class-name="org.jboss.jca.adapters.jdbc.extensions.oracle.OracleExceptionSorter"/>
    </validation>
</datasource>
```

- Edit the configuration file *cef_edelivery_path/conf/domibus/domibus.properties* and configure the datasources as indicated below.

Remark:

Configure the database dialect as it is pre-configured for MySQL by default.

```
#EntityManagerFactory
domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class=oracle.jdbc.xa.client.OracleXADataSource
domibus.entityManagerFactory.jpaProperty.hibernate.dialect=org.hibernate.dialect.Oracle10gDialect
```


4. Configure your Keystore based on §5.1.2 – ["Certificates"](#).
5. Run the standalone server:
 - For Windows under *cef_edelivery_path\domibus\bin*
 - **standalone.bat --server-config=standalone-full.xml**
 - For Linux under *cef_edelivery_path/domibus/bin/*
 - **standalone.sh --server-config=standalone-full.xml**
6. Display the Domibus home page in your browser: <http://localhost:8080/domibus-wildfly> (by default: User = **admin**; Password = **123456**).

Remark:

It is recommended to change the passwords for the default users. See §9.1 – "Administration " for further information.

If you can access the page it means the deployment was successful.

Expected result:



4.4.2. Single Server Deployment

In this section we assume that WildFly (9 or 12 version) is installed at the location `cef_edelivery_path/domibus`.

For this step, you will have to use the following resources (see section §3.1-"[Binaries repository](#)" for the download location):

- **domibus-distribution-X.Y.Z-wildfly-war.zip** (WildFly 9) **or domibus-distribution-X.Y.Z-wildfly12-war.zip** (WildFly 12)
 - **domibus-distribution-X.Y.Z-wildfly-configuration.zip** (WildFly 9) **or domibus-distribution-X.Y.Z-wildfly12-configuration.zip** (WildFly 12)
1. Follow steps **2** (MySQL) or **3** (Oracle) from the §4.4.1 – "[Pre-Configured Single Server Deployment](#)".
 2. Configure the environment variables under `cef_edelivery_path/domibus/bin/standalone.conf`:

```
.....
JAVA_OPTS="-Xms128m -Xmx1024m
java.net.preferIPv4Stack=true"
JAVA_OPTS="$JAVA_OPTS -Ddomibus.config.location=$JBOSS_HOME/conf/domibus
```

-
3. Download and unzip **domibus-distribution-X.Y.Z-wildfly-configuration.zip** (WildFly 9) or **domibus-distribution-X.Y.Z-wildfly12-configuration.zip** (WildFly 12) in the directory *cef_edelivery_path/conf/domibus*.
 4. Configure your Keystore based on §5.1.2 – "Certificates".
 5. Configure the JMS resources:

Configure the JMS resources in the configuration file *cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml* by adding the **jms-connection-factories** and **jms-queues**.

```
<address-settings>
    <!--default for catch all-->
    <address-setting match="#">
        <dead-letter-address>jms.queue.DLQ</dead-letter-address>
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <max-size-bytes>10485760</max-size-bytes>
        <page-size-bytes>2097152</page-size-bytes>
        <message-counter-history-day-limit>10</message-counter-history-day-limit>
    </address-setting>
    <address-setting match="jms.queue.DomibusSendMessageQueue">
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <redelivery-delay>1000</redelivery-delay>
        <max-delivery-attempts>1</max-delivery-attempts>
    </address-setting>
    <address-setting match="jms.queue.DomibusPullMessageQueue">
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <redelivery-delay>1000</redelivery-delay>
        <max-delivery-attempts>1</max-delivery-attempts>
    </address-setting>
    <address-setting match="jms.queue.DomibusBusinessMessageOutQueue">
        <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <redelivery-delay>300000</redelivery-delay>
        <max-delivery-attempts>10</max-delivery-attempts>
    </address-setting>
    <address-setting match="jms.queue.DomibusNotifyBackendJmsQueue">
        <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <redelivery-delay>300000</redelivery-delay>
        <max-delivery-attempts>10</max-delivery-attempts>
    </address-setting>
    <address-setting match="jms.queue.DomibusErrorNotifyConsumerQueue">
        <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <redelivery-delay>300000</redelivery-delay>
        <max-delivery-attempts>10</max-delivery-attempts>
    </address-setting>
    <address-setting match="jms.queue.DomibusErrorNotifyProducerQueue">
        <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
        <expiry-address>jms.queue.ExpiryQueue</expiry-address>
        <redelivery-delay>300000</redelivery-delay>
        <max-delivery-attempts>10</max-delivery-attempts>
    </address-setting>
    <address-setting match="jms.queue.DomibusBusinessMessageInQueue">
        <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
```

```
<expiry-address>jms.queue.ExpiryQueue</expiry-address>
<redelivery-delay>300000</redelivery-delay>
<max-delivery-attempts>10</max-delivery-attempts>
</address-setting>
<address-setting match="jms.queue.DomibusPluginToBackendQueue">
    <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
    <expiry-address>jms.queue.ExpiryQueue</expiry-address>
    <redelivery-delay>300000</redelivery-delay>
    <max-delivery-attempts>10</max-delivery-attempts>
</address-setting>
<address-setting match="jms.queue.DomibusNotifyBackendWebServiceQueue">
    <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
    <expiry-address>jms.queue.ExpiryQueue</expiry-address>
    <redelivery-delay>300000</redelivery-delay>
    <max-delivery-attempts>10</max-delivery-attempts>
</address-setting>
<address-setting match="jms.queue.DomibusUnknownReceiverQueue">
    <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
    <expiry-address>jms.queue.ExpiryQueue</expiry-address>
    <redelivery-delay>300000</redelivery-delay>
    <max-delivery-attempts>10</max-delivery-attempts>
</address-setting>
<address-setting match="jms.queue.DomibusNotifyBackendQueue">
    <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
    <expiry-address>jms.queue.ExpiryQueue</expiry-address>
    <redelivery-delay>300000</redelivery-delay>
    <max-delivery-attempts>10</max-delivery-attempts>
</address-setting>
<address-setting match="jms.queue.DomibusClusterCommandTopic">
    <dead-letter-address>jms.queue.DomibusDLQ</dead-letter-address>
    <expiry-address>jms.queue.ExpiryQueue</expiry-address>
    <redelivery-delay>10000</redelivery-delay>
    <max-delivery-attempts>3</max-delivery-attempts>
</address-setting>
</address-settings>
.....
<subsystem xmlns="urn:jboss:domain:messaging:3.0">
    <hornetq-server>
        <jmx-management-enabled>true</jmx-management-enabled>
        <jms-connection-factories>
.....
        <connection-factory name="edeliveryConnectionFactory">
            <connectors>
                <connector-ref connector-name="in-vm"/>
            </connectors>
            <entries>
                <entry name="java:/jms/ConnectionFactory"/>
            </entries>
            <compress-large-messages>false
            </compress-large-messages>
            <failover-on-initial-connection>false
            </failover-on-initial-connection>
            <use-global-pools>true</use-global-pools>
        </connection-factory>
.....
    </jms-connection-factories>
    <jms-destinations>
.....

```

```
<jms-queue name="DomibusBusinessMessageOutQueue">
    <entry name="java:/jms/domibus.backend.jms.outQueue"/>
    <entry name="java:/jms/queue/DomibusBusinessMessageOutQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusNotifyBackendJmsQueue">
        <entry name="java:/jms/domibus.notification.jms"/>
        <entry name="java:/jms/queue/DomibusNotifyBackendJmsQueue"/>
    <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusErrorNotifyConsumerQueue">
        <entry name="java:/jms/domibus.backend.jms.errorNotifyConsumer"/>
        <entry name="java:/jms/queue/DomibusErrorNotifyConsumerQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusErrorNotifyProducerQueue">
        <entry name="java:/jms/domibus.backend.jms.errorNotifyProducer"/>
        <entry name="java:/jms/queue/DomibusErrorNotifyProducerQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusBusinessMessageInQueue">
        <entry name="java:/jms/domibus.backend.jms.inQueue"/>
        <entry name="java:/jms/queue/DomibusBusinessMessageInQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusPluginToBackendQueue">
        <entry name="java:/jms/domibus.backend.jms.replyQueue"/>
        <entry name="java:/jms/queue/DomibusPluginToBackendQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusSendMessageQueue">
        <entry name="java:/jms/domibus.internal.dispatch.queue"/>
        <entry name="java:/jms/queue/DomibusSendMessageQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusNotifyBackendWebServiceQueue">
        <entry name="java:/jms/domibus.notification.webservice"/>
        <entry name="java:/jms/queue/DomibusNotifyBackendWebServiceQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusUnknownReceiverQueue">
        <entry name="java:/jms/domibus.internal.notification.unknown"/>
        <entry name="java:/jms/queue/DomibusUnknownReceiverQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DomibusNotifyBackendQueue">
        <entry name="java:/jms/domibus.internal.notification.queue"/>
        <entry name="java:/jms/queue/DomibusNotifyBackendQueue"/>
        <durable>true</durable>
    </jms-queue>
    <jms-queue name="DLQ">
        <entry name="java:/jms/domibus/ DLQ"/>
        <entry name="java:/jms/queue/DLQ"/>
        <durable>true</durable>
    </jms-queue>
    <jms-topic name="DomibusClusterCommandTopic">
        <entry name="java:/jms/domibus.internal.command"/>
        <entry name="java:/jms/topic/DomibusClusterCommandTopic"/>
    </jms-topic>
```

```
</jms-topic>
.....
</jms-destinations>
</hornetq-server>
</subsystem>
```

Remark:


Please note that the JMX management also has to be enabled so the JMS resources can be monitored in the JMS Monitoring screen.

6. Configure the executor services:


Configure the executor services in the configuration file
cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml.

```
<subsystem xmlns="urn:jboss:domain:ee:3.0">
.....
<concurrent>
.....
<managed-executor-services>
  <managed-executor-service name="domibusExecutorService" jndi-name="java:jboss/ee/concurrency/executor/DomibusExecutorService" context-service="default" hung-task-threshold="60000" core-threads="5" max-threads="25" keepalive-time="5000"/>
</managed-executor-services>
<managed-executor-services>
  <managed-executor-service name="quartzExecutorService" jndi-name="java:jboss/ee/concurrency/executor/QuartzExecutorService" context-service="default" hung-task-threshold="0" long-running-tasks="true" core-threads="5" max-threads="25" keepalive-time="5000"/>
</managed-executor-services>
.....
</concurrent>
.....
<subsystem xmlns="urn:jboss:domain:ee:3.0">
```


7. Connect to the Admin Console of WildFly at <http://localhost:9990/console>:




8. Click on **Deployments** in the console menu then click on **Add**:



9. Select **Upload a new deployment** then click **Next**:



10. Browse to the location of the **domibus-distribution-X.Y.Z-wildfly.war** (WildFly 9) or **domibus-distribution-X.Y.Z-wildfly12.war** (WildFly 12) file, select it and click **Next** :



11. The deployment is successful when the name of the .war file appears in the Deployment column.

Expected result:

The screenshot shows the WildFly Administration Console with the 'Deployments' tab selected. The left sidebar lists a deployment named 'domibus-distribution-X.Y.Z-wildfly.war', which is circled with a red marker. The main content area displays deployment-related information and common configuration tasks.

4.4.3. Clustered Deployment

For this step, you will have to use the following resources (see section §3.1–“Binaries repository” for the download location):

- **domibus-distribution-X.Y.Z-wildfly-configuration.zip** (WildFly 9) or **domibus-distribution-X.Y.Z-wildfly12-configuration.zip** (WildFly 12)
- **domibus-distribution-X.Y.Z-wildfly-war.zip** (WildFly 9) or **domibus-distribution-X.Y.Z-wildfly12-war.zip** (WildFly 12)

In this section we assume that the setup of WildFly (9 or 12 version) in domain mode has already been done and that the cluster has been enabled as described in the official documentation. For more details on how to perform an installation of WildFly (9 or 12 version) in domain mode, please refer to the official documentation (cf.[REF4]).




Figure 3 - Diagram representing the Deployment of Domibus in a Cluster on WildFly

In order to install Domibus in a WildFly cluster please follow the steps below:

1. Download and unzip **domibus-distribution-X.Y.Z-wildfly-configuration.zip** (for WildFly 9) or **domibus-distribution-X.Y.Z-wildfly12-configuration.zip** (for WildFly 12) in a shared location that is accessible by all the nodes from the cluster. We will refer to this directory as **cef_shared_edelivery_path/Domibus**.
2. Follow steps **2** (MySQL) or **3** (Oracle) from the §4.4.1 – "Pre-Configured Single Server Deployment".

Remarks:

- *This step needs to be performed on all the nodes from the cluster*
- *In the following 2 steps we will edit the profile **full-ha** from the configuration file **domain/configuration/domain.xml** located in the master node*


3. Configure the JMS queues and topics as indicated in §4.4.2 point 5 – "Configure the JMS resources".
4. Configure the database dialect as indicated in §4.4.1 point 3 – "Edit the configuration file **cef_edelivery_path/conf/domibus/domibus.properties**"
5. Configure the environment variables in the file **bin/domain.conf**.

Remark:

bin/domain.conf is located in each WildFly node. The environment variable setting needs to be performed in every node from the cluster.

```
.....
JAVA_OPTS="-Xms128m -Xmx1024m
-java.net.preferIPv4Stack=true"
JAVA_OPTS="$JAVA_OPTS -Ddomibus.config.location=cef_shared_edelivery_path/conf/domibus
```

-
6. Deploy the **domibus-distribution-X.Y.Z-wildfly.war** (for WildFly 9) or **domibus-distribution-X.Y.Z-wildfly12.war** (for WildFly 12) to the cluster. We will use the WildFly Administration console for performing the deployment. We will deploy the application on the **other-server-group** cluster which is configured step by step in the official documentation (cf.[REF4]).



WildFly 9.0.2.Final

Messages: 5 | admin ▾

Home Deployments Configuration Runtime Access Control Patching

Browse By Server Group (2) Deployment (0) Add

Content Repository > Q: []

Unassigned Content > main-server-group > Q: [] No items!

Server Groups > other-server-group >

Add deployment to server group 'other-server-group'

Verify Upload Need Help?


Name: (circled)

Runtime Name:

Enable: (boxed)

Cancel << Back Finish (boxed)

Server Group
Server group other-server-group does not contain deployments.



5. DOMIBUS CONFIGURATION

Domibus exposes the Message Service Handler endpoint as `../services/msh`. Only this endpoint has to be reachable by the other AS4 Access Points and it is typically exposed on the internet.

If the Default WS Plugin (§6.1.2 – "*WS Plugin*") is deployed, Domibus exposes the Default WS Plugin endpoint as `../services/backend`. This endpoint should ONLY be exposed to the backend client(s) within the trusted zone and it should not be exposed to the internet.




Figure 4 - Message Service Handler diagram

5.1. Security Configuration

5.1.1. *Security Policies*

The WS-Security policy used by Domibus when exchanging messages can be specified in the PMode configuration file (§77 – "Pmode Configuration").

Security policy assertions are based on the **WS-Policy framework**.

As requested by the eDelivery AS4 profile, Domibus supports all three mechanisms to reference a security token, as described below.

Domibus distribution includes one policy file for each mechanism (`cef_edelivery_path/conf/domibus/policies/`):

eDeliveryAS4Policy.xml - Reference to a Subject Key Identifier

The <wsse:SecurityTokenReference> element contains a <wsse:KeyIdentifier> element that specifies the token data by means of a X.509 SubjectKeyIdentifier reference. A subject key identifier MAY only be used to reference an X.509v3 certificate.

eDeliveryAS4Policy_BST.xml - Reference to a Binary Security Token

The <wsse:SecurityTokenReference> element contains a wsse:Reference> element that references a local <wsse:BinarySecurityToken> element or a remote data source that contains the token data itself.

eDeliveryAS4Policy_IS.xml - Reference to an Issuer and Serial Number

The <wsse:SecurityTokenReference> element contains a <ds:X509Data> element that contains a <ds:X509IssuerSerial> element that uniquely identifies an end entity certificate by its X.509 Issuer and Serial Number.

For the connectivity with other APs, the three policies may be combined to obtain the required references for initiator/responder and signing/encryption tokens.

5.1.2. Certificates

The certificates that are used for signing and encrypting the messages when communicating with the other Access Points can be configured in the property file located under ***cef_edelivery_path/conf/domibus/domibus.properties***.

By default Domibus is pre-configured to use self-signed certificates. Please note that self-signed certificates should be used only for testing purposes and are not intended for production use.

In order to configure Domibus to use custom certificates the following properties need to be modified:

```
#The location of the keystore
domibus.security.keystore.location=${domibus.config.location}/keystores/gateway_keystore.jks
#Type of the used keystore
domibus.security.keystore.type=jks
#The password used to load the keystore
domibus.security.keystore.password=test123

#Private key
#The alias from the keystore of the private key
domibus.security.key.private.alias=blue_gw
#The private key password
domibus.security.key.private.password=test123

#Truststore
#The location of the truststore
domibus.security.truststore.location=${domibus.config.location}/keystores/gateway_truststore.jks
#Type of the used truststore
domibus.security.truststore.type=jks
#The password used to load the trustStore
domibus.security.truststore.password=test123
```

1. Create, if not present, a folder ***cef_edelivery_path/conf/domibus/keystores***.

2. Get your key pair from an external provider. (Self-signed certificates should only be used for testing purposes, not production). If you are interested in using the CEF Public Key Infrastructure Solution (cf.[REF5]).
3. Create, if not present, the public and private keys containers (e.g. `truststore.jks` and `keystore.jks`).
4. Import your private key into your keystore.

Remarks:

- *Your private key and your keystore should always stay secret. Please never share them.*
- *The keystore alias has to be the same as the party*
- *It is strongly recommended to put your key pair (private and public key) and the public key of the other participants you trust in two separate containers.*

5.2. Domibus Properties

The following properties defined in the property file `cef_edelivery_path/conf/domibus/domibus.properties` can be used to configure Domibus:

| Configuration Property | Default value | Purpose |
|--------------------------------------------------------------|----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>domibus.database.general.schema</code> | <code>general_schema</code> | Multi-tenancy only: Schema used by Domibus to configure the association of users to domains, the super users and other things that are not related to a specific domain. This property is mandatory for multi-tenancy mode. |
| <code>domibus.msh.messageid.suffix</code> | <code>domibus.eu</code> | This Property is used to generate the random Message id with a fixed suffix which is set by default to "domibus.eu". The resulting format will be <code>UUID@\$domibus.msh.messageid.suffix</code> . This property is mandatory. |
| <code>domibus.msh.retry.cron</code> | <code>0/5 * * * *</code> | It is the retry cron job to send the messages. It is set by default to every 5 seconds. This property is mandatory |
| <code>domibus.dispatch.ebms.error.unrecoverable.retry</code> | <code>true</code> | This property should be set to true if Domibus needs to retry sending the failed messages. This property is mandatory |
| <code>domibus.smlzone</code> | <code>acc.edelivery.tech.ec.europa.eu</code> | Set the SMLZone if Domibus needs to be used under Dynamic discovery model. This property is only mandatory if an SML is used. |
| <code>domibus.dynamicdiscovery.useDynamicDiscovery</code> | <code>false</code> | Whether dynamic discovery is used or not. |
| <code>domibus.dynamicdiscovery.client.specification</code> | <code>OASIS</code> | The property specifies the dynamic discovery client to be used for the dynamic process. Possible values: OASIS and PEPPOL. |
| <code>domibus.dynamicdiscovery.peppolclient.mode</code> | <code>TEST</code> | This information is passed to the PEPPOL client that needs to know whether the usage is for PRODUCTION or TESTING mode. |

| | | |
|-------------------------------------------------------------------------------------------|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| domibus.dynamicdiscovery.oasisclient.regexCertificateSubjectValidation | | Apart from validating response of signer certificates against the truststore, the Oasis Dynamic Discovery Client gives the possibility to add (optional) a regular expression to validate any certificate metadata related to the subject of the signer certificate. Example: <code>domibus.dynamicdiscovery.oasisclient.regexCertificateSubjectValidation="^.*EHEALTH_SMP.*\$"</code> |
| domibus.dynamicdiscovery.partyid.responder.role | | The role of the responder PartyId may be defined here (default values are: <code>urn:fdc:peppol.eu:2017:roles:ap:as4</code> for PEPPOL and <code>http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/responder</code> for OASIS) |
| domibus.dynamicdiscovery.partyid.type=urn:oasis:names:tc:ebcore:partyid-type:unregistered | | The type of the PartyId may be defined here (default values are: <code>urn:fdc:peppol.eu:2017:identifiers:ap</code> for PEPPOL and <code>urn:oasis:names:tc:ebcore:partyid-type:unregistered</code> for OASIS) |
| domibus.backend.jmsInQueue | domibus.backend.jms.inQueue | This queue is the entry point for messages to be sent by the sending MSH. This property is only mandatory if the JMS plugin is used. |
| domibus.jms.queue.pull | domibus.internal.pull.queue | Domibus internal queue used for dispatching the pull requests |
| domibus.deployment.clustered | false | If true the quartz scheduler jobs are clustered. This property is mandatory, it should be set to true if the deployment of Domibus is done in a cluster. |
| messageFactoryClass | | The factory for creating SOAPMessage objects Default values - Tomcat/WebLogic: <code>com.sun.xml.internal.messaging.saaj.soap.ver1_2.SOAPMessageFactory1_2Impl</code> - WildFly: <code>com.sun.xml.messaging.saaj.soap.ver1_2.SOAPMessageFactory1_2Impl</code> |
| domibus.dispatcher.allowChunking | true | Allows chunking when sending messages to other Access Points |
| domibus.dispatcher.chunkingThreshold | 104857600 | If <code>domibus.dispatcher.allowChunking</code> is true, this property sets the threshold at which messages start getting chunked(in bytes). Messages under this limit do not get chunked. Defaults to 100 MB. |
| domibus.dispatcher.concurrency | 5-20 | Specify concurrency limits via a "lower-upper" String, e.g. "5-10", or a simple upper limit String, e.g. "10" (the lower limit will be 1 in this case) #when sending messages to other Access Points. |
| domibus.msh.pull.cron | 0 0 0/1 * * ? | Cron expression used for configuring the message puller scheduling. |
| domibus.pull.queue.concurrency | 1-1 | Number of threads used to parallelize the pull requests. |
| domibus.pull.request.send.per.job.cycle | 1 | Number of pull requests executed every cron cycle. |
| domibus.retentionWorker.cronExpression | 0/60 * * * * ? | Cron expression used for configuring the retention worker scheduling. The retention worker deletes the expired messages (downloaded and not-downloaded). |

| | | |
|---------------------------------------------|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| message.retention.downloaded.max.delete | 50 | This property is used to tweak the maximum downloaded messages to be deleted by the retention worker. |
| message.retention.not_downloaded.max.delete | 50 | This property is used to tweak the maximum not-downloaded messages to be deleted by the retention worker. |
| domibus.attachment.storage.location | - | <p>It is possible to configure Domibus to save the message payloads on the file system instead of the database. This setting is recommended when exchanging payloads bigger than 30MB.</p> <p>In order to enable the file system storage please add the following property:</p> <pre>domibus.attachment.storage.location=your_file_system_location</pre> <p>where <i>your_file_system_location</i> is the location on the file system where the payloads will be saved.</p> <p>Remark: In a cluster configuration the file system storage needs to be accessible by all the nodes from the cluster.</p> |
| domibus.taskExecutor.threadCount | 50 | Tomcat only: customize the task executor threads count. |
| domibus.jmx.user | jmsManager | WebLogic specific: the user that will be used to access the queues via JMX. |
| domibus.jmx.password | jms_Manager1 | WebLogic specific: the associated password of the configured domibus.jmx.user. |
| domibus.sendMessage.messageIdPattern | <code>^[\x20-\x7E]*\$</code> | <p>When an initiator backend client submits messages to Domibus for transmission, with the message id field populated, then the message id should be RFC2822 compliant. The pattern specified here ensures this validation.</p> <p>This field is optional. In case the existing client does not match this message id pattern during submission, then this property can be omitted to skip the validation.</p> |
| domibus.listPendingMessages.maxCount | 10000 for Tomcat 500 for WildFly and Weblogic | <p>This property specifies the maximum number of messages that would be served when the 'listPendingMessages' operation is invoked. Setting this property is expected to avoid timeouts due to huge resultsets being served.</p> <p>A value of 0 would return all the pending messages.</p> <p>This property is optional. Omitting this property would default the resultset size to 500.</p> <p>Note: For Tomcat server, the maximum number of shown messages in queue monitoring is defined by the 'domibus.listPendingMessages.maxCount' property.</p> |

| | | |
|--------------------------------------------|---------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| domibus.fourcornermodel.enabled | true | This property affects the GUI search and behaviour. If the property is set to false, 'Final Recipient' and 'Original Sender' criteria disappear from Messages Filter, Messages column picker and from Message details in the GUI. The internal SQL queries for User and Signal Message do not use TB_PROPERTY.NAME = 'finalRecipient' and 'originalSender' anymore. |
| domibus.dispatcher.connectionTimeout | 240000 | For connection between the access points – C2 & C3. Specifies the amount of time, in milliseconds, that the consumer will attempt to establish a connection before it times out. 0 is infinite. |
| domibus.dispatcher.receiveTimeout | 240000 | For connection between the access points – C2 & C3. Specifies the amount of time, in milliseconds, that the consumer will wait for a response before it times out. 0 is infinite. |
| domibus.msh.retry.tolerance | 10800000 | Timeout tolerance for retry messages (in miliseconds). Scheduled retries that, due to any reason, were not performed within this period will be timeout. |
| domibus.sendMessage.failure.delete.payload | false | Whether to delete the message payload or send failure. Defaults to false (the admin could put the message back in the send queue) . |
| domibus.auth.unsecureLoginAllowed | true | The property specifies if authentication is required or not. |
| domibus.pmode.dao.implementation | CachingPModeProvider | Internal configuration provider for managing the PMode access. |
| compressionBlacklist | application/vnd.etsi.asic-s+zip,image/jpeg | The list of mime-types that will not be compressed (in outgoing messages) even if compression is turned on for the given message. |
| domibus.security.keystore.location | \${domibus.config.location}/key stores/gateway_keystore.jks | The location of the keystore. |
| domibus.security.keystore.type | jks | The type of the used keystore. |
| domibus.security.keystore.password | test123 | The password used to load the keystore. |
| domibus.security.key.private.alias | blue_gw | The alias from the keystore of the private key. |
| domibus.security.key.private.password | test123 | The private key password. |
| domibus.security.truststore.location | \${domibus.config.location}/key stores/gateway_truststore.jks | The location of the truststore. |
| domibus.security.truststore.type | jks | The type of the used keystore. |
| domibus.security.truststore.password | test123 | The password used to load the trustStore. |

| | | |
|-------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| domibus.entityManagerFactory.packagesToScan | eu.domibus | Packages to be scanned (comma separated) by the EntityManagerFactory. |
| domibus.entityManagerFactory.jpaProperty.hibernate.connection.driver_class | | The JDBC driver class used for connecting to the database. |
| domibus.entityManagerFactory.jpaProperty.hibernate.dialect | | This property makes Hibernate generate the appropriate SQL for the chosen database. |
| domibus.entityManagerFactory.jpaProperty.hibernate.format_sql | true | Pretty print the SQL in the log and console. |
| domibus.entityManagerFactory.jpaProperty.transaction.factory_class | | The classname of a TransactionFactory to use with Hibernate Transaction API. |
| domibus.entityManagerFactory.jpaProperty.hibernate.transaction.manager_lookup_class | | The classname of the TransactionManagerLookup. |
| com.atomikos.icatch.output_dir | <code> \${domibus.work.location:\${domibus.config.location}}/work/transactions</code> | Tomcat only: Specifies the directory in which to store the debug log files for Atomikos. |
| com.atomikos.icatch.log_base_dir | <code> \${domibus.work.location:\${domibus.config.location}}/work/transactions/log</code> | Tomcat only: Specifies the directory in which the log files should be stored. |
| com.atomikos.icatch.default_jta_timeout | 60000 | Tomcat only: The default timeout for JTA transactions. |
| com.atomikos.icatch.max_timeout | 300000 | Tomcat only: The default transaction max timeout for JTA transactions |
| domibus.jms.XAConnectionFactory.maxPoolSize | 20 | Tomcat only: The max pool size of the JMS connection factory. |
| activeMQ.broker.host | localhost | Tomcat only: The host of the JMS broker. |
| activeMQ.brokerName | localhost | Tomcat only: The name of the JMS broker. |
| activeMQ.embedded.configurationFile | <code>file://\${domibus.config.location}/internal/activemq.xml</code> | Tomcat only: The configuration file of the embedded ActiveMQ broker. In case an external broker is used this property is not needed and it should be deleted from the property file. |
| activeMQ.JMXURL | <code>service:jmx:rmi:///\${activeMQ.broker.host}:\${activeMQ.rmiServerPort}/jndi/rmi:///\${activeMQ.broker.host}:\${activeMQ.connectorPort}/jmxrmi</code> | Tomcat only: The service URL of the MBeanServer. |
| activeMQ.connectorPort | 1199 | Tomcat only: The port that the JMX connector will use for connecting to ActiveMQ. |
| activeMQ.rmiServerPort | 1200 | Tomcat only: The RMI server port. |
| activeMQ.transportConnector.uri | <code>tcp://\${activeMQ.broker.host}:61616</code> | Tomcat only: The connection URI that the clients can use to connect to an ActiveMQ broker using a TCP socket. |

| | | |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| activeMQ.username | domibus | Tomcat only: The username that is allowed to connect to the ActiveMQ broker. |
| activeMQ.password | changeit | Tomcat only: The password of the username defined in the activeMQ.username property. |
| domibus.datasource.xa.xaDataSourceClassName | com.mysql.jdbc.jdbc2.optional.MysqlXADataSource | Tomcat only(XA datasource): The fully qualified underlying XADataSource class name. |
| domibus.datasource.xa.maxLifetime | 60 | Tomcat only(XA datasource): Sets the maximum amount of seconds that a connection is kept in the pool before it is destroyed automatically. |
| domibus.datasource.xa.minPoolSize | 5 | Tomcat only(XA datasource): Sets the minimum pool size. The amount of pooled connections will not go below this value. The pool will open this amount of connections during initialization. |
| domibus.datasource.xa.maxPoolSize | 100 | Tomcat only(XA datasource): Sets the maximum pool size. The amount of pooled connections will not go above this value. |
| domibus.database.serverName | localhost | Tomcat only(XA datasource): The host name or the IP address of the database server. |
| domibus.database.port | 3306 | Tomcat only(XA datasource): The port number of the database server. |
| domibus.datasource.xa.property.user | edelivery | Tomcat only(XA datasource): A user who has access to the Domibus database schema. |
| domibus.datasource.xa.property.password | edelivery | Tomcat only(XA datasource): The password of the user defined in the domibus.datasource.xa.property.user property. |
| domibus.database.schema | domibus | Tomcat only: the Domibus database schema |
| domibus.datasource.xa.property.url | jdbc:mysql://\${domibus.database.serverName}:\${domibus.database.port}/domibus?pinGlobalTxToPhysicalConnection=true | Tomcat only(XA datasource): The JDBC URL connection. It re-uses the properties for the user and password defined above. |
| domibus.datasource.driverClassName | com.mysql.jdbc.Driver | Tomcat only(Non-XA datasource): the JDBC driver class name. |
| domibus.datasource.url | jdbc:mysql://localhost:3306/domibus?useSSL=false | Tomcat only(Non-XA datasource): The JDBC URL connection. |
| domibus.datasource.user | edelivery | Tomcat only(Non-XA datasource): A user who has access to the Domibus database schema. |
| domibus.datasource.password | edelivery | Tomcat only(Non-XA datasource): The password of the user defined in the domibus.datasource.user property. |
| domibus.receiver.certificate.validation.onsending | true | If activated Domibus will verify before sending a User Message if the receiver's certificate is valid and not revoked. If the receiver's certificate is not valid or it has been revoked Domibus will not send the message and it will mark it as SEND_FAILURE |

| | | |
|---------------------------------------------------|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| domibus.sender.certificate.validation.onsending | true | If activated Domibus will verify before sending a User Message if his own certificate is valid and not revoked. If the certificate is not valid or it has been revoked, Domibus will not send the message and it will mark it as SEND_FAILURE (default is true) |
| domibus.sender.certificate.validation.onreceiving | true | If activated Domibus will verify before receiving a User Message if the sender's certificate is valid and not revoked. If the certificate is not valid or it has been revoked, Domibus will not accept the message (default is true) |
| domibus.sender.trust.validation.onreceiving | false | An extra security validation that requires that the party name reflected in the alias of the sender public key should also be contained in the subject of the certificate. |
| domibus.console.login.maximum.attempt | 5 | Maximum connection attempts before the account gets locked (suspended). |
| domibus.console.login.suspension.time | 60 | Property defining how many minutes the account remains locked (suspended) before it is automatically unlocked by the system. |
| domibus.UI.title.name=Domibus | Domibus | Property where you can specify the title in the Tab of Admin Console |

| Configuration Property | Default value | Purpose |
|-----------------------------|---------------|-------------------------------------------------------------------------------------------------|
| Proxy Settings | | In case your Access Point has to use a proxy server you can configure it with these properties. |
| domibus.proxy.enabled | false | true/false depending on whether you need to use proxy or not. |
| domibus.proxy.http.host | - | Host name of the proxy server. |
| domibus.proxy.http.port | - | Port of Proxy server |
| domibus.proxy.user | - | Username for authentication on the proxy server. |
| domibus.proxy.password | - | Password. |
| domibus.proxy.nonProxyHosts | - | Indicates the hosts that should be accessed without going through the proxy. |

Table 1 - Domibus Properties

6. PLUGIN MANAGEMENT

This section describes the different types of plugins and their registration process.

6.1. Default Plugins

Domibus comes with three default plugins. The three Interface Control Documents (ICD) describe these three plugins (JMS, WS and File System Plugin) (cf.[REF6]).

6.1.1. JMS Plugin

For the JMS plugin, you will have to use the following resources (see section § 3.1-"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-default-jms-plugin.zip**

6.1.2. WS Plugin

For the WS plugin, you will have to use the following resources (see section §3.1-"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-default-ws-plugin.zip**

6.1.2.1. *Domibus authentication*

The default web service plugin includes an example of how to implement authentication and authorization. By default this feature is disabled to insure backwards compatibility with older versions of Domibus.

The documentation below answers the question "*how to enable and use the authentication in the WS plugin?*"

The default WS plugin supports:

- Basic Authentication
- X509 Certificates Authentication
- Blue Coat Authentication

Remark:

Blue Coat is the name of the reverse proxy at the Commission. It forwards the request in HTTP with the certificate details inside the request ("Client-Cert" header key).

When more than one authentication method is used, the Basic Authentication takes precedence on both http and https.

When no Basic Authentication is provided, X509 certificates are expected on https requests.

When no Basic Authentication is provided, Blue Coat certificates are expected on http requests.

6.1.2.2. Domibus Authorization

For convenience, the WS plugin uses exactly the same database as configured for Domibus core to store the users/passwords and certificate ids. To learn more about authorization (and authentication), please refer to the plugin cookbook (cf.[REF6]).

There are two default users already inserted in the database (make sure you already ran the migration scripts):

- *admin* and *user* both with **123456** as password.
- *admin* has the role **ROLE_ADMIN** and *user* has the role **ROLE_USER**.

Roles:

ROLE_ADMIN has the permission to call:

- submitMessage with any value for originalSender property
- retrieveMessage (any message among messages notified to this plugin)
- listPendingMessages will list all pending messages for this plugin
- getStatus and getMessageErrors

ROLE_USER has the permission to call:

- submitMessage with originalSender equal to the originalUser
- retrieveMessage, only if finalRecipient equals the originalUser
- listPendingMessages, only messages with finalRecipient equal to the originalUser
- getStatus for its own messages

6.1.2.3. Enable the authentication in Domibus

To enable the authentication at Domibus level the following steps must be configured:

1. In **conf/domibus/domibus.properties**, set the property “**domibus.auth.unsecureLoginAllowed**” to false:

```
domibus.auth.unsecureLoginAllowed=false
```

2. The application server must be configured to allow https requests and pass the authentication credentials to Domibus.

6.1.3. File System Plugin

For the File System plugin, you will have to use the following resources (see section §3.1-"Binaries repository" for the download location):

- **domibus-distribution-X.Y.Z-default-fs-plugin.zip**

6.2. Custom Plugin

Users can develop their own plugins. Please refer to the plugin cookbook for more details (cf.[REF6]).

6.2.1. Plugin registration

Remark:

Please refer to section 9.1.4 - "Message Filtering" for the routing of the specific plugin after registering the plugin on your specific Application Server.

6.2.1.1. Tomcat

In order to install a custom plugin for Tomcat, please follow the steps below:

1. Stop Tomcat server
2. Copy the custom plugin jar file to the plugins folder
CATALINA_HOME/conf/domibus/plugins/lib
3. Copy the custom plugin XML configuration file to
CATALINA_HOME/conf/domibus/plugins/config
4. Start Tomcat server

Remark:

CATALINA_HOME is the folder where the Tomcat is installed.

6.2.1.2. WebLogic

In order to install a custom plugin for WebLogic please follow the steps below:

1. Stop the WebLogic server
2. Copy the custom plugin jar file to the plugins folder
DOMAIN_HOME/conf/domibus/plugins/lib
3. Copy the custom plugin XML configuration file to
DOMAIN_HOME/conf/domibus/plugins/config
4. Start the WebLogic server

Remark:

DOMAIN_HOME is the folder corresponding to the WebLogic domain.

6.2.1.3. WildFly

In order to install a custom plugin please follow the steps below:

1. Stop the WildFly server
2. Copy the custom plugin jar file to the plugins folder **cef_edelivery_path /conf/domibus/plugins/lib**
3. Copy the custom plugin XML configuration file to **cef_edelivery_path /conf/domibus/plugins/config**
4. Start the WildFly server

6.3. Plugin notifications

Domibus core notifies the plugins on different events. The types of events are:

**MESSAGE RECEIVED, MESSAGE SEND FAILURE, MESSAGE RECEIVED FAILURE,
MESSAGE SEND SUCCESS, MESSAGE STATUS CHANGE**

For each plugin, it is possible in the configuration file (*-plugin.xml) to specify the list of events for which it requires notifications. This list is optional and passed as a constructor argument to the NotificationListener bean.

Example:

```
<util:list id="requiredNotificationsList" value-type="eu.domibus.common.NotificationType">

    <value>MESSAGE_RECEIVED</value>

    <value>MESSAGE_SEND_FAILURE</value>

    <value>MESSAGE_STATUS_CHANGE</value>

</util:list>

<bean id="webserviceNotificationListenerService"
      class="eu.domibus.plugin.NotificationListenerService"
      c:queue-ref="notifyBackendWebServiceQueue" c:mode="PULL"
      p:backendConnector-ref="backendWebservice"/>

    p:backendConnector-ref="backendWebservice">

    <constructor-arg ref="requiredNotificationsList"/>

</bean>
```

This list is optional. By default, PULL plugins receive notifications for **MESSAGE RECEIVED, MESSAGE SEND FAILURE, MESSAGE RECEIVED FAILURE** while the **PUSH** plugins receive notification for all events.

7. PMODE CONFIGURATION

Processing Modes (PModes) are used to configure Access Points. The PMode parameters are loaded into the Access Point via an XML file.

The features described in the PMode file are: Security, Reliability, Transport, Business Collaborations, Error Reporting, Message Exchange Patterns (MEPs) and Message Partition Channels (MPCs).

As different messages may be subject to various types of processing or, as different business domains may have several requirements, Access Points commonly support several PModes. Some PMode parameters are mandatory, others are optional. For more information please refer to the [Access Point Component Offering Document](#).

7.1. Configuration

In Domibus, PModes are XML files that you can create or edit. You can configure the two files given: `cef_edelivery_path/conf/pmodes/domibus-gw-sample-pmode-party_id_name1.xml` and `cef_edelivery_path/conf/pmodes/domibus-gw-sample-pmode-party_id_name2.xml`.

The "`party_id_name1`" value must be replaced with your own party name and the "`party_id_name2`" with your corresponding party name.

The `party_id` must match the alias of the certificate in the keystore and the endpoint must be the external access link to your instance.

Remark:

This step could be managed by a PMode Configuration Manager, known to your Business Owner.

```
<party name="party_id_name2"
      endpoint="http://party_id_name2_hostname:8080/domibus/services/msh">
  <identifier partyId="party_id_name2_1"
              partyIdType="partyTypeUrn"/>
</party>
<party name="party_id_name1"
      endpoint="http://party_id_name1_hostname:8080/domibus/services/msh">
  <identifier partyId="party_id_name1_1" partyIdType="partyTypeUrn"/>
</party>
```

Figure 5 - PMode view

7.1.1. Adding a new participant

If a new participant's Access Point is joining your network, you need to configure your PMode accordingly and re-upload it like mentioned in §7.1.4 – ["Upload new Configuration"](#).

- Add a "new_party" element:

```
<party name="new_party_name"
      endpoint="http://new_party_msh">
  <identifier partyId="new_party_id" partyIdType="partyTypeUrn"/>
```

```
</party>
```

- Add your "new_party_name" as initiator:

The party with the role of initiator will be the sender of the messages:

```
<initiatorParties>
    ...
    <initiatorParty name="new_party_name"/>
</initiatorParties>
```

- Add your "new_party_name" as responder:

The party with the role of responder will be the receiver of the messages:

```
<responderParties>
    ...
    <responderParty name="new_party_name"/>
</responderParties>
```

7.1.2. Sample PMode file

Processing modes (PModes) describe how messages are exchanged between AS4 partners (in this case *Access Points blue_gw and red_gw*). These files contain the identifiers of each AS4 Access Point (identified as *parties* in the PMode file below).

Sender and Receiver Identifiers represent the organizations that send and receive the business documents. They are both used in the authorization process (PMode). Therefore, adding, modifying or deleting a participant implies modifying the corresponding PMode files.

Here is an example of a PMode XML file:

Remark:

In this setup, we have allowed each party (blue_gw or red_gw) to initiate the process. If only blue_gw is supposed to send messages, then put only blue_gw in <initiatorParties> and red_gw in <responderParties>.

```
<?xml version="1.0" encoding="UTF-8"?>
<db:configuration xmlns:db="http://domibus.eu/configuration" party="blue_gw">

    <mpcs>
        <mpc name="defaultMpc"
            qualifiedName="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/defaultMPC"
            enabled="true"
            default="true"
            retention_downloaded="0"
            retention_undownloaded="14400"/>
    </mpcs>
    <businessProcesses>
        <roles>
            <role name="defaultInitiatorRole"
                value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/initiator"/>
            <role name="defaultResponderRole"
                value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/responder"/>
        </roles>
    </businessProcesses>
</db:configuration>
```

```

</roles>
<parties>
    <partyIdTypes>
        <partyIdType name="partyTypeUrn"
value="urn:oasis:names:tc:ebcore:partyid-type:unregistered"/>
    </partyIdTypes>
    <party name="red_gw"
        endpoint="http://<red_hostname>:8080/domibus/services/msh">
            <identifier partyId="domibus-red" partyIdType="partyTypeUrn"/>
        </party>
    <party name="blue_gw"
        endpoint="http://<blue_hostname>:8080/domibus/services/msh">
            <identifier partyId="domibus-blue" partyIdType="partyTypeUrn"/>
        </party>
    </parties>
    <meps>
        <mep name="oneway" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/oneway"/>
        <mep name="twoway" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/twoWay"/>
            <binding name="push" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/push"/>
            <binding name="pushAndPush" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/push-and-push"/>
    </meps>
    <properties>
        <property name="originalSenderProperty"
            key="originalSender"
            datatype="string"
            required="true"/>
        <property name="finalRecipientProperty"
            key="finalRecipient"
            datatype="string"
            required="true"/>
        <propertySet name="eDeliveryPropertySet">
            <propertyRef property="finalRecipientProperty"/>
            <propertyRef property="originalSenderProperty"/>
        </propertySet>
    </properties>
    <payloadProfiles>
        <payload name="businessContentPayload"
            cid="cid:message"
            required="true"
            mimeType="text/xml"/>
        <payload name="businessContentAttachment"
            cid="cid:attachment"
            required="false"
            mimeType="application/octet-stream"/>
        <payloadProfile name="MessageProfile" maxSize="40894464"> <!-- maxSize is
currently ignored -->
            <attachment name="businessContentPayload"/>
            <attachment name="businessContentAttachment"/>
        </payloadProfile>
    </payloadProfiles>
    <securities>
        <security name="eDeliveryAS4Policy"
            policy="eDeliveryAS4Policy.xml"/>
    </securities>

```

```

                signatureMethod="RSA_SHA256" />
            </securities>
            <errorHandlings>
                <errorHandling name="demoErrorHandling"
                    errorAsResponse="true"
                    businessErrorNotifyProducer="true"
                    businessErrorNotifyConsumer="true"
                    deliveryFailureNotifyProducer="true"/>
            </errorHandlings>
            <agreements>
                <agreement name="agreement1" value="A1" type="T1"/>
            </agreements>
            <services>
                <service name="testService1" value="bdx:noprocess" type="tc1"/>
                <service name="testService" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/service"/>
            </services>
            <actions>
                <action name="tc1Action" value="TC1Leg1"/>
                <action name="testAction" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/test"/>
            </actions>
            <as4>
                <receptionAwareness name="receptionAwareness" retry="12;4;CONSTANT"
duplicateDetection="true"/>
                <reliability name="AS4Reliability" nonRepudiation="true"
replyPattern="response"/>
            </as4>
            <legConfigurations>
                <legConfiguration name="pushTestcase1tc1Action"
                    service="testService1"
                    action="tc1Action"
                    defaultMpc="defaultMpc"
                    reliability="AS4Reliability"
                    security="eDeliveryAS4Policy"
                    receptionAwareness="receptionAwareness"
                    propertySet="eDeliveryPropertySet"
                    payloadProfile="MessageProfile"
                    errorHandling="demoErrorHandling"
                    compressPayloads="true"/>
                <legConfiguration name="testServiceCase"
                    service="testService"
                    action="testAction"
                    defaultMpc="defaultMpc"
                    reliability="AS4Reliability"
                    security="eDeliveryAS4Policy"
                    receptionAwareness="receptionAwareness"
                    propertySet="eDeliveryPropertySet"
                    payloadProfile="MessageProfile"
                    errorHandling="demoErrorHandling"
                    compressPayloads="true"/>
            </legConfigurations>
        <process name="tc1Process"
            mep="oneway"
            binding="push"
            initiatorRole="defaultInitiatorRole"
            responderRole="defaultResponderRole">
            <initiatorParties>

```

```

<initiatorParties>
    <initiatorParty name="blue_gw"/>
    <initiatorParty name="red_gw"/>
</initiatorParties>
<responderParties>
    <responderParty name="blue_gw"/>
    <responderParty name="red_gw"/>
</responderParties>
<legs>
    <leg name="pushTestcase1tc1Action"/>
    <leg name="testServiceCase"/>
</legs>
</process>
</businessProcesses>
</db:configuration>

```

7.1.3. Domibus PMode configuration to ebMS3 PMode Mapping

The following table provides additional information concerning the Domibus PMode configuration files.

| Domibus PMode Configuration | EbMS3 Specification [ebMS3CORE] [AS4-Profile] | Description |
|------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MPCs | - | Container which defines the different MPCs (Message Partition Channels). |
| MPC | PMode[1].BusinessInfo.MPC: The value of this parameter is the identifier of the MPC (Message Partition Channel) to which the message is assigned. It maps to the attribute Messaging / UserMessage | Message Partition Channel allows the partition of the flow of messages from a <i>Sending MSH</i> to a <i>Receiving MSH</i> into several flows, each of which is controlled separately. An MPC also allows merging flows from several <i>Sending MSHs</i> into a unique flow that will be treated as such by a <i>Receiving MSH</i> . The value of this parameter is the identifier of the MPC to which the message is assigned. |
| MessageRetentionDownloaded | - | Retention interval for messages already delivered to the backend. |
| MessageRetentionUnDownloaded | - | Retention interval for messages not yet delivered to the backend. |
| Parties | - | Container which defines the different PartyIdTypes, Party and Endpoint. |
| PartyIdTypes | maps to the attribute Messaging/UserMessage/PartyInfo | Message Unit bundling happens when the Messaging element contains multiple child elements or Units (either User Message Units or Signal Message Units). |

| | | |
|------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Party ID | maps to the element Messaging/UserMessage/PartyInfo | The ebCore Party ID type can simply be used as an identifier format and therefore as a convention for values to be used in configuration and – as such – does not require any specific solution building block. |
| Endpoint | maps to PMode[1].Protocol.Address | The endpoint is a party attribute that contains the link to the MSH. The value of this parameter represents the address (endpoint URL) of the <i>Receiver MSH</i> (or <i>Receiver Party</i>) to which Messages under this PMode leg are to be sent. Note that a URL generally determines the transport protocol (e.g. if the endpoint is an email address, then the transport protocol must be SMTP; if the address scheme is "http", then the transport protocol must be HTTP). |
| AS4 | - | Container. |
| Reliability [@Nonrepudiation] [@ReplyPattern] | Nonrepudiation maps to PMode[1].Security.SendReceipt.NonRepudiation ReplyPattern maps to PMode[1].Security.SendReceipt.ReplyPattern | PMode[1].Security.SendReceipt.No nRepudiation : value = 'true' (to be used for non-repudiation of receipt), value = 'false' (to be used simply for reception awareness). PMode[1].Security.SendReceipt.ReplyPattern: value = 'Response' (sending receipts on the HTTP response or back-channel). PMode[1].Security.SendReceipt.ReplyPattern: value = 'Callback' (sending receipts use a separate connection). |
| ReceptionAwareness [@retryTimeout] [@retryCount] [@strategy] [@duplicateDetection] | retryTimeout maps to PMode[1].ReceptionAwareness.Retry=true PMode[1].ReceptionAwareness.Retry.Parameters retryCount maps to PMode[1].ReceptionAwareness.Retry.Parameters strategy maps to PMode[1].ReceptionAwareness.Retry.Parameters duplicateDetection maps to PMode[1].ReceptionAwareness.DuplicateDetection | These parameters are stored in a composite string. <ul style="list-style-type: none">• <i>retryTimeout</i> defines timeout in seconds.• <i>retryCount</i> is the total number of retries.• <i>strategy</i> defines the frequency of retries. The only <i>strategy</i> available as of now is <i>CONSTANT</i>.• <i>duplicateDetection</i> allows to check duplicates when receiving twice the same message. The only <i>duplicateDetection</i> available as of now is <i>TRUE</i>. |
| Securities | - | Container. |
| Security | - | Container. |

| | | |
|------------------------------|------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Policy | PMode[1].Security.* NOT including PMode[1].Security.X509.Signature.Algorithm | The parameter defines the name of a WS-SecurityPolicy file. |
| SignatureMethod | PMode[1].Security.X509.Signature.Algorithm | This parameter is not supported by WS-SecurityPolicy and therefore it is defined separately. |
| BusinessProcessConfiguration | - | Container. |
| Agreements | maps to eb: Messaging/ UserMessage/ CollaborationInfo/ AgreementRef | This OPTIONAL element occurs zero times or once. The <i>AgreementRef</i> element is a string that identifies the entity or artifact governing the exchange of messages between the parties. |
| Actions | - | Container. |
| Action | maps to Messaging/ UserMessage/ CollaborationInfo/Action | This REQUIRED element occurs once. The element is a string identifying an operation or an activity within a Service that may support several of these |
| Services | - | Container. |
| ServiceTypes Type | maps to Messaging/ UserMessage/ CollaborationInfo/ Service[@type] | This REQUIRED element occurs once. It is a string identifying the service that acts on the message and it is specified by the designer of the service. |
| MEP [@Legs] | - | An ebMS MEP defines a typical choreography of ebMS User Messages which are all related through the use of the referencing feature (RefToMessageId). Each message of an MEP Access Point refers to a previous message of the same Access Point, unless it is the first one to occur. Messages are associated with a label (e.g. <i>request, reply</i>) that precisely identifies their direction between the parties involved and their role in the choreography. |
| Bindings | - | Container. |
| Binding | - | The previous definition of ebMS MEP is quite abstract and ignores any binding consideration to the transport protocol. This is intentional, so that application level MEPs can be mapped to ebMS MEPs independently from the transport protocol to be used. |
| Roles | - | Container. |

| | | |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Role | <p>Maps to PMode.Initiator.Role or PMode.Responder.Role depending on where this is used. In ebMS3 message this defines the content of the following element:</p> <ul style="list-style-type: none"> • For Initiator: Messaging/UserMessage/PartyInfo/From/Role • For Responder: Messaging/UserMessage/PartyInfo/To/Role | <p>The required role element occurs once, and identifies the authorized role (<i>fromAuthorizedRole</i> or <i>toAuthorizedRole</i>) of the Party sending the message (when present as a child of the <i>From</i> element), or receiving the message (when present as a child of the <i>To</i> element). The value of the role element is a non-empty string, with a default value of http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultRole</p> <p>Other possible values are subject to partner agreement.</p> |
| Processes | - | Container. |
| PayloadProfiles | - | Container. |
| Payloads | - | Container. |
| Payload | maps to PMode[1].BusinessInfo.PayloadProfile | <p>This parameter allows specifying some constraint or profile on the payload. It specifies a list of payload parts.</p> <p>A payload part is a data structure that consists of five properties:</p> <ol style="list-style-type: none"> 1. name (or Content-ID) that is the part identifier, and can be used as an index in the notation PayloadProfile; 2. MIME data type (text/xml, application/pdf, etc.); 3. name of the applicable XML Schema file if the MIME data type is text/xml; 4. maximum size in kilobytes; (currently not used) 5. Boolean string indicating whether the part is expected or optional, within the User message. <p>The message payload(s) must match this profile.</p> |
| ErrorHandleings | - | Container. |
| ErrorHandling | - | Container. |

| | | |
|-------------------------------|--------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ErrorAsResponse | maps to PMode[1].ErrorHandling.Report.AsResponse | This Boolean parameter indicates (if <i>true</i>) that errors generated from receiving a message in error are sent over the back-channel of the underlying protocol associated with the message in error. If <i>false</i> , such errors are not sent over the back-channel. |
| ProcessErrorNotifyProducer | maps to PMode[1].ErrorHandling.Report.ProcessErrorNotifyProducer | This Boolean parameter indicates whether (if <i>true</i>) the Producer (application/party) of a User Message matching this PMode should be notified when an error occurs in the Sending MSH, during processing of the <i>User Message to be sent</i> . |
| ProcessErrorNotifyConsumer | maps to PMode[1].ErrorHandling.Report.ProcessErrorNotifyProducer | This Boolean parameter indicates whether (if <i>true</i>) the Consumer (application/party) of a User Message matching this PMode should be notified when an error occurs in the Receiving MSH, during processing of the <i>received User message</i> . |
| DeliveryFailureNotifyProducer | maps to PMode[1].ErrorHandling.Report.DeliveryFailuresNotifyProducer | When sending a message with this reliability requirement (<i>Submit</i> invocation), one of the two following outcomes shall occur: - The Receiving MSH successfully delivers (<i>Deliver</i> invocation) the message to the Consumer. - The Sending MSH notifies (<i>Notify</i> invocation) the Producer of a delivery failure. |
| Legs | - | Container. |

| | | |
|---------|---|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Leg | - | Because messages in the same MEP may be subject to different requirements - e.g. the reliability, security and error reporting of a response may not be the same as for a request – the PMode will be divided into <i>legs</i> . Each user message label in an ebMS MEP is associated with a PMode leg. Each PMode leg has a full set of parameters for the six categories above (except for <i>General Parameters</i>), even though in many cases parameters will have the same value across the MEP legs. Signal messages that implement transport channel bindings (such as PullRequest) are also controlled by the same categories of parameters, except for <i>BusinessInfo group</i> . |
| Process | - | In <i>Process</i> everything is plugged together. |

Table 2 - Domibus PMode configuration to ebMS3 mapping

7.1.4. Upload new Configuration

7.1.4.1. Upload the PMode file


Remark:

In case of a cluster environment, the PMode configuration is replicated automatically on all the nodes.

1. To update the PMode configuration and/or Truststore, connect to the Administration Console using the administrator's credentials (by default: User = **admin**; Password = **123456**) to <http://localhost:8080/domibus>.

Remark:

*It is recommended to change the passwords for the default users.
See §9.1 – "Administration" for further information.*



2. Click on the **PMode** menu:

```

<?xml version="1.0" encoding="UTF-8"?>
<db:configuration xmlns:db="http://domibus.eu/configuration" party="blue_gw">

<mpcs>
    <mpc name="defaultMpc"
        qualifiedName="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultMPC"
        enabled="true"
        default="true"
        retention_download="0"
        retention_undownloaded="14400"/>
</mpcs>
<businessProcesses>
    <roles>
        <role name="defaultInitiatorRole"
            value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/initiator"/>
        <role name="defaultResponderRole"
            value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/responder"/>
    </roles>
    <parties>
        <partyIdTypes>
            <partyIdType name="partyTypeUrn" value="urn:oasis:names:tc:ebcore:partyId-type:unregistered"/>
        </partyIdTypes>
        <party name="red_gw"
            endpoint="http://40.118.20.112:8083/domibus/services/msh"
            allowChunking="false">
            <identifier partyId="domibus-red" partyIdType="partyTypeUrn"/>
        </party>
        <party name="blue_gw" />
    </parties>
</businessProcesses>

```

3. Press the **Upload** button:

The screenshot shows the Domibus Administration Console interface. On the left, a sidebar lists various management options: Messages, Message Filter, Error Log, PMode (which is selected), JMS Monitoring, Truststore, and Users. The main content area is titled "PMode" and displays an XML configuration file. At the bottom of this area are two buttons: "Upload" and "Download". The "Upload" button is circled in red.

```
<?xml version="1.0" encoding="UTF-8"?>
<db:configuration xmlns:db="http://domibus.eu/configuration" party="blue_gw">

<mpcs>
    <mpc name="defaultMpc"
        qualifiedName="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultMPC"
        enabled="true"
        default="true"
        retention_downloaded="0"
        retention_undownloaded="14400"/>
</mpcs>
<businessProcesses>
    <roles>
        <role name="defaultInitiatorRole"
            value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/initiator"/>
        <role name="defaultResponderRole"
            value="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/responder"/>
    </roles>
    <parties>
        <partyIdTypes>
            <partyIdType name="partyTypeUrn" value="urn:oasis:names:tc:ebcore:partyid-type:unregistered"/>
        </partyIdTypes>
        <party name="red_gw"
            endpoint="http://40.118.20.112:8083/domibus/services/msh"
            allowChunking="false">
            <identifier partyId="domibus-red" partyIdType="partyTypeUrn"/>
        </party>
        <party name="blue_gw" />
    </parties>
</businessProcesses>

```

4. Press the **Choose File** button, and navigate to the PMode file, select it and click on the **Open** button (or equivalent) in the standard dialog box:

The screenshot shows the same PMode configuration page as the previous one. However, a file selection dialog box is now overlaid on the screen. This dialog is titled "Upload File" and contains a "Choose File" button, which is highlighted with a red box. In the background, the XML configuration code is partially visible, and at the bottom, there are "Upload" and "Download" buttons.

5. Once the file has been selected, click "OK" to upload the PMode xml file:

The screenshot shows the Domibus Administration Console interface. On the left, there is a sidebar with the following menu items: Messages, Message Filter, Error Log, PMode (which is currently selected), JMS Monitoring, Truststore (highlighted with a red box), and Users. The main content area is titled 'PMode' and displays an XML configuration snippet. A modal dialog box titled 'Upload File' is overlaid on the page. It contains a 'Choose File' button followed by the path 'domibus-gw...de-blue.xml'. At the bottom of the dialog are two buttons: 'OK' (highlighted with a red box) and 'Cancel'. Below the dialog, there are 'Upload' and 'Download' buttons.

Remark:


Every time a PMode is updated, the truststore is also reloaded from the filesystem.

7.1.4.2. Upload the Truststore


1. Select the "Truststore" menu and press the **Upload** button:

The screenshot shows the Domibus Administration Console interface. On the left, there is a sidebar with the following menu items: Messages, Message Filter, Error Log, PMode, JMS Monitoring, Truststore (highlighted with a red box), and Users. The main content area is titled 'Truststore' and displays a table of truststore entries. The table has columns: Name, Subject, Issuer, Valid from, and Valid until. Two entries are listed: 'blue_gw' and 'red_gw'. Both entries have the same subject and issuer values. The 'Valid from' and 'Valid until' fields show specific dates and times. Below the table, a message says '0 selected / 2 total'. At the bottom left, there is a large blue 'Upload' button, which is highlighted with a red box.

2. Navigate to the Truststore and select it by clicking on the **Open** button (or equivalent) of the standard file open dialog:



3. Once the file has been selected, enter the keystore password and click on the **OK** button to activate the new **truststore jks file**:



8. SPECIAL SCENARIO: SENDER AND RECEIVER ARE THE SAME

In this special scenario, the Sender Access Point acts also as the Receiver Access Point. Multiple backends can exchange messages via the same Access Point using the same or different plugins.

8.1. PMode Configuration

A party (e.g. **blue_gw**) which is Sender and Receiver must be defined in both the `<initiatorParties>` and `<responderParties>` sections as shown below:

```
....  
    <initiatorParties>  
        .....  
        <initiatorParty name="blue_gw"/>  
        .....  
    </initiatorParties>  
    <responderParties>  
        .....  
        <responderParty name="blue_gw"/>  
        .....  
    </responderParties>  
....
```

8.2. Message structure

A message that is sent to the same Access Point will have to contain the same party id in both **From** and **To** sections. Below there is an example of a message sent using the Default WS Plugin:

```
<ns:UserMessage>  
...  
    <ns:PartyInfo>  
        <ns:From>  
            <ns:PartyId type="urn:oasis:names:tc:ebcore:partyid-type:unregistered">domibus-blue</ns:PartyId>  
            <ns:Role>http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/initiator</ns:Role>  
        </ns:From>  
        <ns:To>  
            <ns:PartyId type="urn:oasis:names:tc:ebcore:partyid-type:unregistered">domibus-blue</ns:PartyId>  
            <ns:Role>http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/responder</ns:Role>  
        </ns:To>  
    </ns:PartyInfo>  
....
```

8.3. Message ID convention

Due to some limitations related to the uniqueness of the message identifier, a convention has been defined in this scenario. The message ID used for the received message is derived from the message ID used for the sent message with the following rule: the suffix "_1" is added to the sent message id.

Example:

sent message ID is **ae15851e-78fb-4b51-aac8-333c08c450d6@domibus**

received message ID is **ae15851e-78fb-4b51-aac8-333c08c450d6@domibus_1**

9. ADMINISTRATION TOOLS

9.1. Administration Console

9.1.1. Changing passwords

It is recommended to change the passwords for the default users, who are allowed to have access to the Domibus Administration Console, mainly **admin** and **user**.


- In order to change the password for a user, navigate to the **Users** menu entry to obtain the list of configured users:

| Username | Role | Password | Active | Actions |
|-------------|------------|----------|-------------------------------------|---------|
| w7 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> | |
| w10 | ROLE_ADMIN | ***** | <input type="checkbox"/> | |
| w11 | ROLE_ADMIN | ***** | <input type="checkbox"/> | |
| w8989898989 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> | |


- To edit the user details, click on the **EDIT** icon (in RED). DO NOT click on the BIN icon as this would **DELETE** the record.

| Username | Role | Password | Active | Actions |
|----------|------------|----------|-------------------------------------|---------|
| w7 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> | |
| w10 | ROLE_ADMIN | ***** | <input type="checkbox"/> | |
| w11 | ROLE_ADMIN | ***** | <input type="checkbox"/> | |
| w8 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> | |


3. In the popup window, choose a new password using the rules shown:



4. Confirm the password:



5. Click on OK:



- When done, either click on **Save**, to save the new password or **Cancel** to leave the password unchanged.

| Username | Role | Password | Active | Actions |
|---------------|------------|----------|-------------------------------------|---------|
| w7 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> | |
| w10 | ROLE_ADMIN | ***** | <input type="checkbox"/> | |
| w11 | ROLE_ADMIN | ***** | <input type="checkbox"/> | |
| w898989898989 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> | |

9.1.2. User Account Lockout Policy


A user account lockout policy has been implemented on Domibus Admin Console. By default, if a user tries to log to the Admin Console with a wrong password 5 times in a row, his account will be suspended (locked):

You can define in `domibus.properties` (section **5.2 Domibus Properties**) the number of failed attempts after which a user's account will be locked.

By default, a user remains suspended during one hour before his account is automatically unlocked and the user can try to log again.

If the user wants his account to be unlocked without waiting the default one hour, he can ask his administrator to unlock the account. To unlock the account, the administrator must change the user's status on the Admin Console from "Suspended" to "Active".

Select the suspended user and click on "Edit":




| Username | Role | Password | Active | Actions |
|---------------|------------|----------|-----------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| w7 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> |   |
| w10 | ROLE_ADMIN | ***** | <input type="checkbox"/> |   |
| w11 | ROLE_ADMIN | ***** | <input type="checkbox"/> |   |
| w898989898989 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> |   |
| w7777 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> |   |
| w6666 | ROLE_ADMIN | ***** | <input checked="" type="checkbox"/> |   |
| tempUser | ROLE_USER | ***** | <input checked="" type="checkbox"/> |   |
| ttt | ROLE_USER | ***** | <input checked="" type="checkbox"/> |   |
| caroline | ROLE_USER | ***** | <input type="checkbox"/> (Suspended) |   |

0 selected / 19 total

 Cancel  Save  New  Edit  Delete

Re-activate the user (unlock it) by checking the “Active” status and confirming with OK:



User Edit

Username * caroline

Email

Roles* ROLE_ADMIN, ROLE_USER

Password

Confirmation

Active

* required fields (Suspended)

Do not forget to click on **Save** on the next window and then on **Yes** to confirm the change.

9.1.3. Adding new users


1. New users can be added to the existing default users (**admin** and **user**) by clicking on **New**:

The screenshot shows the 'Users' section of the Domibus Administration Console. On the left, there's a sidebar with links like 'Messages', 'Error Log', 'PMode', 'JMS Monitoring', 'Truststore', and 'Users'. The main area has a table with columns: 'Username', 'Role', 'Password', 'Active', and 'Actions'. There are four rows visible: 'w7' (ROLE_ADMIN), 'w10' (ROLE_ADMIN), 'w11' (ROLE_ADMIN), and 'w8' (ROLE_ADMIN). Below the table, it says '0 selected / 19 total'. At the bottom, there are buttons for 'Cancel', 'Save', '+ New' (which is highlighted with a red box), 'Edit', and 'Delete'.


2. For each new user, you must enter a username, an email, a role and a password:

The screenshot shows the 'User Edit' dialog box over the 'Users' list. The dialog has fields for 'Username' (set to 'user'), 'Email', 'Roles*' (a dropdown menu), 'Password', 'Confirmation', and 'Active' (a checked checkbox). At the bottom are 'OK' and 'Cancel' buttons, with 'OK' also highlighted with a red box.

3. Click on **OK**:



4. Again, once the user has been created, do not forget to click on the **Save** button on the **Users** page to register your changes on the system:



9.1.4. Message Filtering

Domibus allows the routing of messages to different plugins, based on some messages attributes:

- **From** : initial sender (C1)
- **To** : final recipient (C4)

- **Action:** defined as 'Leg' in the PMode
- **Service:** as defined in the PMode

The following rules apply:

- Domibus considers the ordered list of 'filters' to route all messages. The first filter matching the filter criteria, will define the target plugin. The order of the plugin is therefore important in the routing process.

Note 1: if the filters are all mutually exclusive, the order would not matter.

Note 2: The 'Persisted' column indicates if the plugin filter configuration has already been saved. If a plugin filter configuration has not already been saved, the 'Persisted' value is unchecked and an error message is shown on the top of the screen. In this case, it is strongly recommended to review the filters configuration and save it afterwards.

| Plugin | From | To | Action | Service | Persisted | Actions |
|-------------------|------|----|--------|---------|--------------------------|-----------------------------------------------------------------------------------|
| backendWebservice | | | | | <input type="checkbox"/> | Move Up Move Down Edit Delete |
| Jms | | | | | <input type="checkbox"/> | Move Up Move Down Edit Delete |

0 selected / 2 total

Move Up Move Down Cancel Save + New Edit Delete

- One plugin may be applied to multiple filters. This is done by the use of the 'OR' criteria. (cf. backendWebservice in the example below).
- Multiple attributes could also be defined in one filter. This is done by the use of the 'AND' criteria. (cf. the first filter in the example below).
- One filter may have no criteria, meaning that all messages (not matching previous filters) will be routed to the corresponding plugin automatically. As a result, subsequent filters will therefore not be considered for any incoming message. In the example below, the last filter routes all remaining messages to plugin 'backendWebservice'.

| Plugin | From | To | Action | Service | Persisted | Actions |
|-------------------|------|----|--------|---------|-----------|---------------------------------------------------------------------------------|
| backendWebservice | Jms | | | | | Edit Delete |

1 selected / 2 total

Move Up Move Down

Cancel Save + New Edit Delete

Figure 9 – Message Filter Page

Use the **New** and **Delete** buttons to create or delete a filter.

As the order matters, move up and down actions allow placing each filter in the right order:

Cf. **Move Up** and **Move Down** buttons.

After some changes have been applied to the filters, the **Cancel** and **Save** buttons become active:

- Press **Cancel** to cancel the changes
- Press **Save** to save the changes and activate them immediately.

The console will ask the user to confirm the operation, before proceeding.

Example of message attributes used for routing and matching the first filter used in the example above:

- **Action** : *TC1Leg1*
- **Service** : *bdx:noprocess:tc2*
- **From** : *domibus-blue:urn:oasis:names:tc:ebcore:partyid-type:unregistered*
- **To** : *domibus-red:urn:oasis:names:tc:ebcore:partyid-type:unregistered*

That information can be found in the incoming message received by Domibus (e.g. see below):

```
<ns:PartyInfo>
  <ns:From>
    <ns:PartyId type="urn:oasis:names:tc:ebcore:partyid-type:unregistered">domibus-blue</ns:PartyId>
    <ns:Role>http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/initiator</ns:Role>
  </ns:From>
  <ns:To>
    <ns:PartyId type="urn:oasis:names:tc:ebcore:partyid-type:unregistered">domibus-red</ns:PartyId>
    <ns:Role>http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/responder</ns:Role>
  </ns:To>
</ns:PartyInfo>
<ns:CollaborationInfo>
  <ns:Service type="tc1">btx:noprocess</ns:Service>
  <ns:Action>TC1Leg1</ns:Action>
</ns:CollaborationInfo>
```

9.2. Message Log

Domibus administration dashboard includes a message logging page that gives the administrator information related to sent messages, received messages and their status (SENT, RECEIVED, FAILED, ACKNOWLEDGED,...).

The following state machines illustrate the evolution of the processing of messages according to the encountered events:




Figure 10 - State machine of Corner 2 (sending access point)




Figure 11 - State machine of Corner 3 (receiving access point)

| Messages | | | | | | | |
|-------------------------------------------------|----------------|---------------|-------------|--------------------------|---------|--------------|---------|
| Message Id | Message Status | From Party Id | To Party Id | Received | AP Role | Message Type | Actions |
| 904c115-a71b-4bc8-91b3-e19b13c24d@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:10GMT+2 | SENDING | USER_MESSAGE | |
| 3ef8401-7b10-4e55-b373-b0414ed94898@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:10GMT+2 | SENDING | USER_MESSAGE | |
| 37297f5-5827-44ea-9e83-595e2e4e11@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:09GMT+2 | SENDING | USER_MESSAGE | |
| c24dd5f4-6a7f-4eaf-8317-5498994df380@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |
| 6206746-6db8-4f68-a2f2-562607bc7c37@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |
| 69b5a6f1-1aa8-4512-9ce9-e5a9e95b0c3e@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |
| 3459a8ff-8c00-4455-8119-12e91cbe31@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |
| 5b50f25-5e5c-4397-bbaa-3bb8b12fb37@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |
| c9f14110-0339-4cc6-88a5-2a95c214aa@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |
| e9e0fbcc-0831-433a-6188-ed5c5f883f0@domibus.eu | ACKNOWLEDGED | domibus-blue | domibus-red | 13-09-2017 15:43:07GMT+2 | SENDING | USER_MESSAGE | |

Figure 12 - Domibus Message Log

Remark:

The administration dashboard is reachable via the following URLs:

http://your_server:your_port_number/domibus (Tomcat)

http://your_server:your_port_number/domibus-wildfly (WildFly)

http://your_server:your_port_number/domibus-weblogic (WebLogic)

9.3. Application Logging

9.3.1. Domibus log files

Domibus has three log files:

1. domibus-security.log : this log file contains all the security related information. For example, you can find information about the clients who connect to the application.
2. domibus-business.log: this log file contains all the business related information. For example, when a message is sent or received, etc.
3. domibus.log : this log file contains both the security and business logs plus miscellaneous logs like debug information, logs from one of the framework used by the application, etc.

| Name | Date modified | Type |
|----------|-----------------|---------------|
| atomikos | 26-Jun-17 10:04 | Text Document |
| business | 22-Jun-17 13:53 | Text Document |
| domibus | 26-Jun-17 16:33 | Text Document |
| security | 22-Jun-17 13:53 | Text Document |

9.3.2. Logging properties

It is possible to modify the configuration of the logs by editing the logging properties file: **cef_edelivery_path/conf/domibus/logback.xml**:

| Name | Date modified | Type |
|-----------|-----------------|-----------------|
| internal | 06-Dec-16 08:52 | File folder |
| keystores | 06-Dec-16 08:52 | File folder |
| plugins | 22-Jun-17 09:44 | File folder |
| policies | 06-Dec-16 08:52 | File folder |
| work | 14-Jun-17 08:01 | File folder |
| domibus | 28-Jun-17 12:22 | PROPERTIES File |
| logback | 22-Jun-17 10:16 | XML Document |

9.3.3. Error Log page

To go to the error log page of the Domibus Admin Console, click on the **Error log** menu entry:

| Message Id | Error Code | Timestamp |
|------------|--------------------------|-----------|
| EBMS_0003 | 14-09-2017 12:14:15GMT+2 | |
| EBMS_0003 | 14-09-2017 12:11:18GMT+2 | |
| EBMS_0003 | 14-09-2017 12:07:37GMT+2 | |
| EBMS_0003 | 14-09-2017 12:06:14GMT+2 | |
| EBMS_0003 | 14-09-2017 12:06:00GMT+2 | |
| EBMS_0003 | 14-09-2017 12:03:00GMT+2 | |

This option lists all the Message Transfers error logs and includes the **ErrorSignalMessageId**, **ErrorDetail** and **Timestamp**. You can sort messages by using the up or down arrow to search for a specific message.

| Message Id | Error Code | Timestamp |
|------------|--------------------------|-----------|
| EBMS_0003 | 14-09-2017 12:14:15GMT+2 | |
| EBMS_0003 | 14-09-2017 12:11:18GMT+2 | |
| EBMS_0003 | 14-09-2017 12:07:37GMT+2 | |
| EBMS_0003 | 14-09-2017 12:06:14GMT+2 | |
| EBMS_0003 | 14-09-2017 12:06:00GMT+2 | |
| EBMS_0003 | 14-09-2017 12:03:00GMT+2 | |

Figure 13 - Domibus – Error Log page

9.4. Queue Monitoring

Domibus uses JMS queues to handle the messages:

| Destination type | JNDI name | Comment | Description |
|------------------|---------------------------------------------|---------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Queue | jms/domibus.internal.dispatch.queue | No redelivery because redelivery of MSH messages is handled via ebMS3/AS4 | This queue is used for scheduling messages for sending via the MSH. |
| Queue | jms/domibus.internal.notification.unknown | | Notifications about received messages (by the MSH) that do not match any backend routing criteria will be sent to this queue. In production environment this queue should be monitored in order to handle those messages manually. |
| Topic | jms/domibus.internal.command | | This topic is used for sending commands to all nodes in a cluster. For example, it is used after a PMode was uploaded in order to notify all nodes to update their PMode cache (in case caching is enabled). |
| Queue | jms/domibus.backend.jms.replyQueue | | This queue is used for sending replies back to the sender of a message. Replies contain: a correlationId, ebMS3 messageId (if possible), error messages (if available). |
| Queue | jms/domibus.backend.jms.outQueue | | Messages received by the MSH (that match the routing criteria for the JMS plugin) will be sent to this queue. |
| Queue | jms/domibus.backend.jms.inQueue | | This queue is the entry point for messages to be sent by the sending MSH. |
| Queue | jms/domibus.backend.jms.errorNotifyConsumer | | This queue is used to inform the receiver of a message that an error occurred during the processing of a received message. |
| Queue | jms/domibus.backend.jms.errorNotifyProducer | | This queue is used to inform the sender of a message that an error occurred during the processing of a message to be sent. |

| | | | |
|--------------|-----------------------------------------|--|---------------------------------------------------------------------------------------------------------------------------------------------|
| Queue | jms/domibus.notification.jms | | Used for sending notifications to the configured JMS plugin. |
| Queue | jms/domibus.internal.notification.queue | | This queue is used to notify the configured plugin about the status of the message to be sent. |
| Queue | jms/domibus.notification.webservice | | Used for sending notifications to the configured WS plugin. |
| Queue | jms/domibus.DLQ | | This is the Dead Letter Queue of the application. The messages from other queues that reached the retry limit are redirected to this queue. |

Table 3 - Queue Monitoring

All these queues can be monitored and managed using the **JMS Monitoring** page, which is accessible from the **JMS Monitoring** menu of the administration console:

Warning:

For Tomcat server, the maximum number of shown messages in the queue monitoring is defined by the 'domibus.listPendingMessages.maxCount' property.

In the **Source** field, we have all the queues listed, along with the number of messages pending in each queue:

If a queue is used internally by the application core, its name will start with **[internal]**. A regular expression is used to identify all the internal queues. The value for this regular expression can be adapted in the **domibus.jms.internalQueue.expression** property from the **cef_edelivery_path/conf/domibus/domibus.properties** file.

In the **JMS Monitoring** page the following operations can be performed:

1. Inspecting and filtering the messages from a queue based on the following fields:
 - a. Signal Message id: identifier of an error signal message
 - b. Message id: identifier of a message
 - c. Error detail: text of the error (full)
 - d. AP Role: role of the AP
 - e. Error Code: structured code of the error
 - f. Source: the source queue of the messages
 - g. Error or Notified Time Period: time interval that will filter the messages based on the send dates
 - h. JMS type: the JMS header **JMSType**
 - i. Selector: the JMS message selector expression

Remark:

For more information on the JMS message headers and the JMS message selector, please check the official documentation at <https://docs.oracle.com/cd/E19798-01/821-1841/bnces/index.html>.

2. Move a message:


a. Move the message from the DLQ to the original queue:

- Select the JMS message from the DLQ and press the **Move** icon (in RED marker):



| ID | Time | Custom prop | JMS prop | Actions |
|----------------------------------------------------|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|
| ID:b4edelivery02-38615-1505217897670-6:15:142:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "3ef762ae-938b-401f-8243-ac929916c6ee@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:142:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "d21ccb3a-a01a-487a-a18f-12169acce553@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:140:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "124997be-f86f-4d06-917b-8dd3335129ac@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:140:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |

- Select the original queue from the **Destination** dropdown list in the dialog box:



| ID | Time | Custom prop | JMS prop | Actions |
|----------------------------------------------------|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|
| ID:b4edelivery02-38615-1505217897670-6:15:142:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "3ef762ae-938b-401f-8243-ac929916c6ee@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:142:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "d21ccb3a-a01a-487a-a18f-12169acce553@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:140:1:1 | 12-09-2017 16:45:10GMT+2 | 0fbdd6a806bb@domibus.eu, "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:140:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |

Click on "Ok" to confirm that you want to move the selected messages
WARNING: This operation will be executed immediately and cannot be reverted.
Click on "Cancel" to leave the message untouched.

Destination:

- Press the **Ok** button in the dialog, and the message will be moved to the original queue.

Note: the details of a message can be viewed by selecting it (double-clicking) from the message list:

The screenshot shows a modal dialog box titled "JMS Message". It displays the following information:

- Header**: Source: domibus.notification.webservice
- Id**: ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1
- Timestamp**: 12-09-2017 16:45:10GMT+2
- JMS Type**
- Custom Properties** (JSON):


```
{
        "MESSAGE_ID": "d21ccb3a-a01a-487a-a18f-12169acce553@domibus.eu",
        "originalQueue": "domibus.notification.webservice",
        "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"
      }
```

At the bottom left is a "Close" button, and at the bottom right are the values "domibus.notification.webservice", "JMSDestination", and "JMSDeliveryMode".

Click **Close** to exit the dialog box.

b. Move multiple messages from the DLQ to the original queue:

- Select multiple JMS messages from the DLQ and press the **Move** icon button:



The screenshot shows a table of JMS messages in the DLQ. The columns are:

- ID
- Time
- Custom prop
- JMS prop
- Actions

The table contains five rows of message data. The "Actions" column for the second row is highlighted with a red circle around the "Move" icon.

| ID | Time | Custom prop | JMS prop | Actions |
|----------------------------------------------------|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|
| ID:b4edelivery02-38615-1505217897670-6:15:142:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "3ef762ae-938b-401f-8243-ac929916c6ee@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:142:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "d21ccb3a-a01a-487a-a18f-12169acce553@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:140:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "124997be-f86f-4d06-917b-8dd3335129a@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:140:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:138:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "179fe63a-bcb7-4820-a38b-0fbd6a806bb@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:138:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:136:1:1 | 12-09-2017 16:45:09GMT+2 | {"MESSAGE_ID": "5c5a9dbc-7043-491c-a1e2-dba7c3889134@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:136:1:1", "JMSDestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |

- Select the original queue from the Destination dropdown list, and click **Ok**.




Remark:

Please make sure that all the selected messages came from the same source queue. Use the filtering capabilities to ensure this.

3. Delete message(s)


a. Delete one or more messages from one queue:

- Select one or several JMS messages from the source queue and press the **Delete** button:



| ID | Time | Custom prop | JMS prop | Actions |
|----------------------------------------------------|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|
| ID:b4edelivery02-38615-1505217897670-6:15:142:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "3ef762ae-938b-401f-8243-ac929916c6ee@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:142:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "d21ccb3a-a01a-487a-918f-12169acce553@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:5:19058:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:140:1:1 | 12-09-2017 16:45:10GMT+2 | {"MESSAGE_ID": "124997be-f86f-4d06-917b-8d335129a@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:140:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:15:136:1:1 | 12-09-2017 16:45:09GMT+2 | {"MESSAGE_ID": "5c5a9dbc-7043-491c-a1e2-dba7c3889134@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:15:136:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:8:19060:1:1 | 12-09-2017 16:45:09GMT+2 | {"MESSAGE_ID": "990003f-3480-437e-be5a-e3dc63fa74f@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:8:19060:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |

- By clicking the **Delete** button, the selected messages are removed from the screen, but you still have to confirm your changes by clicking on the **Save** button. As long as you have not clicked on the **Save** button, your changes are not taken into account in the system.



| ID | Time | Custom prop | JMS prop | Actions |
|----------------------------------------------------|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|
| ID:b4edelivery02-38615-1505217897670-6:8:19058:1:1 | 12-09-2017 16:45:09GMT+2 | {"MESSAGE_ID": "af211692-2b92-4977-8cf4-95835a72f3ff@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:8:19058:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:2:19010:1:1 | 12-09-2017 16:45:08GMT+2 | {"MESSAGE_ID": "37e8bb1a-fdd8-47c2-9bbc-0030b12b631e@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:2:19010:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:9:18986:1:1 | 12-09-2017 16:45:08GMT+2 | {"MESSAGE_ID": "00bde420-bfaf-483e-8ef1-f908a5d22d9@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:9:18986:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:2:126:1:1 | 12-09-2017 16:45:08GMT+2 | {"MESSAGE_ID": "f5420b3b-b4ef-4c59-aa4b-3d41830cfdb@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:2:126:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |
| ID:b4edelivery02-38615-1505217897670-6:18:138:1:1 | 12-09-2017 16:45:07GMT+2 | {"MESSAGE_ID": "fe3721d8-9cac-4cae-b7aa-c3c0ceafe94@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} | {"JMSMessageID": "ID:b4edelivery02-38615-1505217897670-6:18:138:1:1", "JMSEdestination": "queue://domibus.notification.webservice", "JMSDeliveryMode": "PERSISTENT"} | |

- To cancel the changes you made, click on the **Cancel** button instead:

| List of JMS Messages | | | |
|----------------------|----------------------------------------------------|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| | ID | Date | Action |
| | ID:b4edelivery02-38615-1505217897670-6:8:19058:1:1 | 12-09-2017 16:45:09GMT+2 | {"JMSMessageID": "af211692-2b92-4977-8cf9-95835a72f3ff@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} |
| | ID:b4edelivery02-38615-1505217897670-6:2:19010:1:1 | 12-09-2017 16:45:08GMT+2 | {"JMSMessageID": "37e8bb1a-fdd8-47c2-9fb0-0030b12b631@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} |
| | ID:b4edelivery02-38615-1505217897670-6:9:18986:1:1 | 12-09-2017 16:45:08GMT+2 | {"JMSMessageID": "00bde420-bfaf-483e-8ef1-f908a5d22d9f@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} |
| | ID:b4edelivery02-38615-1505217897670-6:22:126:1:1 | 12-09-2017 16:45:08GMT+2 | {"JMSMessageID": "f5420b3b-b4ef-4c59-aa4b-3dc41830cfdb@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} |
| | ID:b4edelivery02-38615-1505217897670-6:18:138:1:1 | 12-09-2017 16:45:07GMT+2 | {"JMSMessageID": "fe3721d8-9cac-4cae-b7aa-c3c0ceafe94@domibus.eu", "originalQueue": "domibus.notification.webservice", "NOTIFICATION_TYPE": "MESSAGE_SEND_SUCCESS"} |

1 selected / 399 total

Cancel Save Move Delete

9.5. Configuration of the queues

Queues should be configured appropriately and according to the backend system needs and re-delivery policy.

9.5.1. Tomcat

Domibus uses ActiveMQ as JMS broker. The various queues are configured in the `cef_edelivery_path/conf/domibus/internal/activemq.xml` file.

Please see [ActiveMQ redelivery policy](#) and configure the parameters below if needed:

```
<redeliveryPlugin fallbackToDeadLetter="true"
    sendToDlqIfMaxRetriesExceeded="true">
<redeliveryPolicyMap>
    <redeliveryPolicyMap>
        <defaultEntry>
            <!-- default policy-->
            <redeliveryPolicy maximumRedeliveries="10"      redeliveryDelay="300000"/>
        </defaultEntry>
        <redeliveryPolicyEntries>
            <redeliveryPolicy queue="domibus.internal.dispatch.queue" maximumRedeliveries="0"/>
            <redeliveryPolicy queue="domibus.internal.pull.queue" maximumRedeliveries="0"/>
        </redeliveryPolicyEntries>
    </redeliveryPolicyMap>
</redeliveryPolicyMap>
</redeliveryPlugin>
```

Access to the JMS messaging subsystem is protected by a username and a password in clear text defined in the Domibus properties file `cef_edelivery_path/conf/domibus/domibus.properties`.

It is recommended to change the password for the default user:

```
activeMQ.username=domibus
activeMQ.password=changeit
```

Remark:

*The user (**activeMQ.username**) and the password (**activeMQ.password**) defined in the **domibus.properties** file are referenced in the authentication section of the **activemq.xml** file provided.*

9.5.2. WebLogic

Please use the admin console of WebLogic to configure the re-delivery limit and delay if necessary.

9.5.3. WildFly

Please use the admin console of WildFly to configure the re-delivery limit and delay if necessary.

10. LARGE FILES SUPPORT

Domibus supports transfers between Access Points of files up to 2 GB using Java 8. In order to compute the message signature, Domibus loads the whole message into memory using a byte array. In Java, byte arrays can hold a maximum of 2 GB hence the Domibus limitation of 2 GB.

If Domibus is started using Java 7 the limitation is 1 GB due to a limitation in Java 7 version.

In order to optimize the sending of such large files, HTTP chunking is activated by default in the connection with the receiver Access Points. As chunked encoding is useful when sending larger amounts of data but decreases the performance on smaller amounts, Domibus uses a threshold to activate the chunking when appropriate only.

The following properties are used to configure chunking: **domibus.dispatcher.allowChunking** and **domibus.dispatcher.chunkingThreshold**. For more information about these properties, please refer to the section [5.2 Domibus Properties](#).

11. DATA ARCHIVING

11.1. What's archiving?

Data archiving consists of moving messages that have been processed successfully or unsuccessfully by the access point to an external storage location for long-term retention.

Archived data consists of older data that have been processed at the communication level by the access points that are still significant to the business and may be needed for future reference. They may also be retained for legal constraints.

Data archives are indexed and searchable to allow easy retrieval.

It is not recommended to use Domibus as an archiving solution. Nevertheless, if the data really needs to be stored for long periods, then it is possible to set the Data Retention Policy to allow it to be extracted from the database through the webservices or through an external archiving tool.

11.2. Data Retention Policy

A data retention policy is a procedure established by the business for continuous information storage for operational, legal or compliance reasons.

The data retention policy needs to be defined based on the business needs and constraints.

In Domibus, the data retention policy can be found in the PMode file:

```
<mpcs>
  <mpc name="defaultMpc"
    qualifiedName="http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/defaultMPC"
    enabled="true"
    default="true"
    retention_downloaded="0"
    retention_undownloaded="14400"/>
</mpcs>
```

In the above extract of the sample PMode configuration of Domibus, the data retention policy is set to **14400 minutes** (10 days) if the message is not downloaded. This means that if the message is not downloaded, it will be deleted and then only the metadata containing the information of the receiver and the acknowledgement will be retained.

The data retention policy is set by default to **0 minutes** if the message is downloaded. This means that the message will be instantaneously deleted as soon as it is downloaded. These two parameters, retention_downloaded and retention_undownloaded, can therefore be modified to meet the needs of the business.

11.3. Data Extraction

In order to keep the metadata and the payload of the message for a longer period than the one set, in the PMode, it is recommended to extract it to an external storage. As long as the retention worker does not delete it, data can be extracted through the webservices or through an external archiving tool.

For more information, please refer to the Data Model provided in the "Domibus Software Architecture Document" that can be found on the CEF Digital single web portal [REF6].

12. NON REPUDIATION

In order to guarantee non-repudiation, the sending Access Point (C2) stores the full **SignalMessage**, including the **MessageInfo**, the Receipt (that contains the **NonRepudiationInformation** for each part) and the signature of the receipt by the receiver Access Point (C3).

This will guarantee that the receiver Access Point (C3) cannot deny having received a message from the sender Access Point (C2) during the sending process. However; if the initial sender (C1) wants to be sure that the final recipient (C4) cannot deny having received a specific content inside this message, then the sender must be able to show the specific content that was used to produce the receiver Access Point (C3) signature.

Domibus, as a sending Access Point (C2), keeps track of the metadata of the sent messages but does not store the actual message payloads. Therefore; it is recommended that the initial sender (C1) stores the message payloads safely for the time needed to guarantee non-repudiation of the sent messages.

In order to guarantee non-repudiation, the receiving Access Point (C3) stores the full **UserMessage** and the associated signature of the sender (C2).

This will guarantee that the sender Access Point (C2) cannot deny having sent a message to the receiver during the sending process. However; if the final recipient (C4) wants to be sure that the sender cannot deny having sent a specific content inside this message, then the final recipient (C4) must be able to show the specific content that was used to produce the sender Access Point signature (C2).

Domibus, as a receiving Access Point (C3), keeps track of the metadata of the received messages and will store the message payloads, only for the (limited) duration configured in the retention period (specified in the PMode). Therefore, it is recommended that the final recipient (C4) either stores the message payloads safely or aligns the retention period on the receiving Access Point (C3) with the time needed to guarantee non-repudiation of the received messages.


13. TLS CONFIGURATION

13.1. TLS Configuration

13.1.1. Transport Layer Security in Domibus

One way of implementing TLS for the eDelivery AS4 profile is to use the TLS in the Domibus Message Handler (MSH) described below, otherwise this would have to be handled at a higher level (e.g. Application Server, Proxy, etc...).

To enable secure communication at the transport layer (TLS) between a sending and a receiving MSH (Access Point), both the client and the server need to be configured accordingly.



The client is used in the initiator MSH to send the request and is therefore configured via CXF while the server is configured at container/application server level.

13.1.2. Client side configuration (One Way SSL)

The **tlsClientParameters** are configured in the `cef_edelivery_path/conf/domibus/clientauthentication.xml` file:

```
<http-conf:tlsClientParameters disableCNCheck="true" secureSocketProtocol="TLSv1.2"
    xmlns:http-conf="http://cxf.apache.org/transports/http/configuration"
    xmlns:security="http://cxf.apache.org/configuration/security">

    <security:trustManagers>
        <security:keyStore type="JKS" password="your_trustore_password"
            file="${domibus.config.location}/keystores/your_trustore_ssl.jks"/>
    </security:trustManagers>

</http-conf:tlsClientParameters>
```

Remark:

your_trustore_ssl is used at the transport layer (SSL) while *your_trustore*, described in §5.1.2 – "Certificates" is used by Domibus to encrypt and sign (WS-Security).

When the **clientauthentication.xml** file is present and the endpoint of the receiving MSH is *https://*, the TLS parameters are added via the CXF framework to the send request.

The version of the TLS must be specified by setting **secureSocketProtocol="TLSv1.2"**.

If you use self-signed certificates you need to set **disableCNCheck="true"**.

The attribute **disableCNCheck** specifies whether JSSE should omit checking if the host name specified in the URL matches the host name specified in the Common Name (CN) of the server's certificate. The attribute is "false" by default and must not be set to "true" during production use (cf.[REF7]).

Remark:

TLSv1.2 is mandatory for eDelivery AS4 Profile.

13.1.3. Client side configuration (Two Way SSL)

The configuration is similar to the one used for *One Way SSL*, except that the **tlsClientParameters** gets configured with both *trustManagers* and *keystoreManagers*. The **clientauthentication.xml** file should look like this:

```
<http-conf:tlsClientParameters disableCNCheck="true" secureSocketProtocol="TLSv1.2"
    xmlns:http-conf="http://cxf.apache.org/transports/http/configuration"
    xmlns:security="http://cxf.apache.org/configuration/security">
    <security:trustManagers>
        <security:keyStore type="JKS" password="your_trustore_password"
            file="${domibus.config.location}/keystores/your_trustore_ssl.jks"/>
    </security:trustManagers>
    <security:keyManagers keyPassword="your_keystore_password">
        <security:keyStore type="JKS" password="your_keystore_password"
            file="${domibus.config.location}/keystores/your_keystore_ssl.jks"/>
    </security:keyManagers>
</http-conf:tlsClientParameters>
```

Remark:

*your_trustore_ssl and your_keystore_ssl are used at the transport layer (SSL) while
your_trustore and your_keystore, described in §5.1.2 – Certificates are used by Domibus to
encrypt and sign (WS-Security).*

Two Way SSL is optional and based on the eDelivery AS4 Profile.

13.1.4. Server side configuration

13.1.4.1. Tomcat 8

In Server.xml, add a new connector with the **SSLEnabled** attribute set to "true":

```
<Connector SSLEnabled="true"
    protocol="org.apache.coyote.http11.Http11NioProtocol"
    port="8443" maxThreads="200"
    scheme="https" secure="true"
    keystoreFile="${domibus.config.location}/keystores/your_keystore_ssl.jks"
    keystorePass="your_keystore_password"
    clientAuth="false" sslProtocol="TLS" />
```

The keystore jks location and password must be specified, otherwise the default ones will be taken into account.

TLS version can also be specified.

The above connector has **clientAuth="false"**, which means that only the server has to authenticate itself (One Way SSL). To configure "Two Way SSL", which is optional in the eDelivery AS4 Profile, set **clientAuth="true"** in Server.xml and provide the location of the *your_truststore_ssl.jks* file so that the server can verify the client:

```
<Connector SSLEnabled="true"
    protocol="org.apache.coyote.http11.Http11NioProtocol"
    port="8443" maxThreads="200"
    scheme="https" secure="true"
    keystoreFile="${domibus.config.location}/keystores/your_keystore_ssl.jks"
    keystorePass="your_keystore_password"
    truststoreFile="${domibus.config.location}/keystores/your_truststore_ssl.jks"
    truststorePass="your_trustore_password"
    clientAuth="true" sslProtocol="TLS" />
```

13.1.4.2. WebLogic

- Specify the use of SSL on default port 7002

Go to Servers → select Server Name → Configuration → General then click on **Client Cert Proxy Enabled**:

SSL Listen Port: 7002

Client Cert Proxy Enabled

- Add keystore and truststore:

Go to Servers → select Server Name → Configuration → Keystores and SSL tabs and use **Custom Identity and Custom Trust** then set keystore and trustore jks.

To disable basic authentication at WebLogic level:

By default WebLogic performs its own basic authentication checks before passing the request to Domibus. As we want basic authentication to be performed by Domibus, we need to disable it at the application server level.

To do so, in **DOMAIN_HOME/config/config.xml**, add:

```
<enforce-valid-basic-auth-credentials>false</enforce-valid-basic-auth-credentials>
```

13.1.4.3. WildFly 9

In the *cef_edelivery_path/domibus/standalone/configuration/standalone-full.xml* file:

- add the keystore and trustore jks file names to the ApplicationRealm:

```
<security-realm name="ApplicationRealm">
<server-identities>
<ssl>
  <keystore path="../conf/domibus/keystores/gateway_keystore.jks" relative-to="jboss.server.base.dir"
  keystore-password="test123" alias="blue_gw" key-password="test123"/>
</ssl>
</server-identities>
<authentication>
  <truststore path="../conf/domibus/keystores/gateway_truststore.jks" relative-
  to="jboss.server.base.dir" keystore-password="test123" />
...
</authentication>
```

- add https-listener to default-server:


```
<subsystem xmlns="urn:jboss:domain:undertow:2.0">
  <buffer-cache name="default"/>
  <server name="default-server">
    <http-listener name="default" socket-binding="http" redirect-socket="https"/>
    <https-listener name="default_https" socket-binding="https" security-realm="ApplicationRealm"
    verify-client="REQUIRED"/>
```

13.1.4.4. Configure Basic and Certificates authentication in SoapUI


Go to File → Preferences → HTTP Settings and check the option **Adds authentication information to outgoing requests:**

| |
|--------------------------------------------------------------------------------------------------------------------------------------|
| <input checked="" type="checkbox"/> Adds authentication information to outgoing request |
| HTTP Version: <input style="width: 20px; height: 20px;" type="button" value="1.1"/> |
| User-Agent Header: <input type="text"/> |
| Request compression: <input type="button" value="None"/> |
| Response compression: <input checked="" type="checkbox"/> Accept compressed responses from hosts |
| Disable Response Decompression: <input type="checkbox"/> Disable decompression of compressed responses |
| Close connections after request: <input type="checkbox"/> Closes the HTTP connection after each SOAP request |
| Chunking Threshold: <input type="text"/> |
| Authenticate Preemptively: <input checked="" type="checkbox"/> Adds authentication information to outgoing request |
| Expect-Continue: <input type="checkbox"/> Adds Expect-Continue header to outgoing request |
| Pre-encoded Endpoints: <input type="checkbox"/> URI contains encoded endpoints, don't try to re-encode |
| Normalize Forward Slashes: <input type="checkbox"/> Replaces duplicate forward slashes in HTTP request endpoints with a single slash |

Go to File → Preferences → SSL Settings, add the **KeyStore** and **KeyStore Password** and check the option **requires client authentication**:



To allow Basic Authentication, select the Auth tab, click Add New Authorization and select Basic. Enter user and password (e.g: Username = **admin**; Password = **123456**)



13.1.4.5. PMode update

If you enable HTTPS then your PMode Configuration Manager needs to make sure that all other endpoint PModes are modified accordingly.

With the SSL connector configured as above, the MSH endpoint is now:
https://your_domibus_host:8443/domibus/services/msh.

After the updates, upload the PModes via the Admin Console:

Example:

```
<party name="party_id_name1"
endpoint=
"https:// party_id_name1_hostname:8443/domibus/services/msh">
```

14. DYNAMIC DISCOVERY OF UNKNOWN PARTICIPANTS

14.1. Overview

In a dynamic discovery setup, the sender and/or the receiver parties and their capabilities are not configured in advance.

The sending Access Point will dynamically retrieve the necessary information for setting up an interoperability process from the Service Metadata Publisher (SMP). The SMP stores the interoperability metadata which is a set of information on the recipient or end entity (its identifier, supported business documents and processes) and AP (metadata which includes technical configuration information on the receiving endpoint, such as the transport protocol and its address) cf.[REF8].

The receiving AP registers its metadata in the SMP and configures the PMode to be able to accept messages from trusted senders that are not previously configured in the PMode. The receiving AP will have to configure one process in its PMode for each SMP entry.

The mapping between the PMode process and the SMP entry is defined in §14.3 – "PMode configuration for PEPPOL" and §14.12 -- "PMode configuration for OASIS".

Please note that the sender does not have to be registered in the SMP and the receiver merely extracts its identifier from the received message.

The following sections describe how to configure Domibus AP in order to use Dynamic Discovery (§14.3 – "PMode configuration for PEPPOL", §14.4 – "Policy and certificates for PEPPOL", §14.12 – "PMode configuration for OASIS", §14.13 – "Policy and certificates for OASIS").

14.2. Domibus configuration for PEPPOL

To enable the integration with the SMP/SML components, Domibus requires some changes in the **domibus.properties** configuration file which include:

1. Adding the following properties to enable the usage of the PEPPOL dynamic discovery client:

```
domibus.dynamicdiscovery.client.specification">PEPPOL
```

2. Setting the dynamic discovery client to use certificates to access the SMP. These certificates are different in TEST and PRODUCTION, therefore we need to specify the Mode used by the dynamic discovery client by setting the following property:

```
domibus.dynamicdiscovery.peppolclient.mode">TEST
```

3. Setting the "**domibus.smlzone**" property.

14.3. PMode configuration for PEPPOL

14.3.1. Sender PMode

In a dynamic discovery process, the receiver of the messages is not known beforehand and therefore the **PMode.Responder** parameter SHOULD NOT be set.

The dynamic discovery process must include a leg which maps the configured entry (action, service and service type – see section 14.9 – "Message format for PEPPOL") of the Receiver in the SMP.

The security policy to be used in the leg is the policy that embeds the Binary Security Token into the security header (see section §5.1.1 – "Security Policies" for more information):

```
security="eDeliveryAS4Policy_BST"
```

Sample Sender PMODE configuration extract:

```
...
<services>
    <service name="testService1"
        value="cenbii-procid-UBL ::urn:www.cenbii.eu:profile:bii05:ver2.0"
        type="urn:fdc:peppol.eu:2017:identifiers:proc-id"/>
</services>
<actions>
    <action name="tc1Action"
        value="urn:oasis:names:specification:UBL:schema:xsd:CreditNote-2::CreditNote##urn:www.cenbii...."/>
</actions>
<securities>
    <security name="eDeliveryAS4Policy_BST"
        policy="eDeliveryAS4Policy_BST.xml"
        signatureMethod="RSA_SHA256"/>
</securities>
<legConfigurations>
    <legConfiguration name="pushTestcase1tc1Action"
        service="testService1"
        action="tc1Action"
        defaultMpc="defaultMpc"
        reliability="AS4Reliability"
        security="eDeliveryAS4Policy_BST"
        receptionAwareness="receptionAwareness"
        propertySet="eDeliveryPropertySet"
        payloadProfile="MessageProfile"
        errorHandling="demoErrorHandling"
        compressPayloads="true"/>
</legConfigurations>
<process name="tc1Process"
        agreement="agreementEmpty"
        mep="oneway"
        binding="push"
        initiatorRole="defaultInitiatorRole"
        responderRole="defaultResponderRole">
    <initiatorParties>
        <initiatorParty name="senderalias"/>
    </initiatorParties>
    <!-- no responderParties element -->
```

```

<legs>
  <leg name="pushTestcase1tc1Action"/>
</legs>
</process>
...

```

14.3.2. Receiver PMode

Dynamic discovery configuration of the receiver is similar to the configuration of the sender, except that the roles are swapped: the sender of the messages is not known beforehand. As a consequence the **PMode.Initiator** parameter SHOULD NOT be set.

```

...
<process name="tc1Process"
  agreement="agreementEmpty"
  mep="oneway"
  inding="push"
  initiatorRole="defaultInitiatorRole"
  responderRole="defaultResponderRole">
  <responderParties>
    <responderParty name="receveralias"/>
  </responderParties>
  <!-- no initiatorParties element -->
  <legs>
    <leg name="pushTestcase1tc1Action"/>
  </legs>
</process>
...

```

14.4. Policy and certificates for PEPPOL

The receiver must include the certificate of the trusted authority(ies) in its truststore. It will only accept messages that were signed with certificates issued by the trusted authority(ies) (cf. §20 – ["Troubleshooting"](#)

[Failed to obtain DB connection from datasource](#)

SEVERE: Exception sending context initialized event to listener instance of class
org.springframework.web.context.ContextLoaderListener

```

org.springframework.beans.factory.BeanCreationException: Error creating bean with name
'org.springframework.scheduling.quartz.SchedulerFactoryBean#0' defined in ServletContext resource [/WEB-
INF/msh-config.xml]: Invocation of init method failed; nested exception is org.quartz.JobPersistenceException:
Failed to obtain DB connection from datasource
'springTxDataSource.org.springframework.scheduling.quartz.SchedulerFactoryBean#0':
com.atomikos.jdbc.AtomikosSQLException: Failed to grow the connection pool [See nested exception:
com.atomikos.jdbc.AtomikosSQLException: Failed to grow the connection pool]
  at
org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.initializeBean(AbstractAuto
wireCapableBeanFactory.java:1578)
  at
org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.doCreateBean(AbstractAuto
wireCapableBeanFactory.java:545)

```

```

at
org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.createBean(AbstractAutowireCapableBeanFactory.java:482)
at
org.springframework.beans.factory.support.AbstractBeanFactory$1.getObject(AbstractBeanFactory.java:305)
at
org.springframework.beans.factory.support.DefaultSingletonBeanRegistry.getSingleton(DefaultSingletonBeanRegistry.java:230)
at
org.springframework.beans.factory.support.AbstractBeanFactory doGetBean(AbstractBeanFactory.java:301)
SEVERE: One or more listeners failed to start. Full details will be found in the appropriate container log file
May 11, 2016 10:12:43 AM org.apache.catalina.util.SessionIdGeneratorBase createSecureRandom
INFO: Creation of SecureRandom instance for session ID generation using [SHA1PRNG] took [13,256]
milliseconds.
May 11, 2016 10:12:43 AM org.apache.catalina.core.StandardContext startInternal
SEVERE: Context [/domibus] startup failed due to previous errors
May 11, 2016 10:12:43 AM org.apache.catalina.core.ApplicationContext log
INFO: Closing Spring root WebApplicationContext
May 11, 2016 10:12:43 AM org.apache.catalina.core.ApplicationContext log
INFO: Shutting down log4j

```

Solution: Setup the password properly in the **domibus.properties**.

14.5. Exception sending context initialized event to listener instance of class

```

SEVERE: Exception sending context initialized event to listener instance of class
org.springframework.web.context.ContextLoaderListener
org.springframework.beans.factory.BeanCreationException: Error creating bean with name
'entityManagerFactory' defined in URL [file:///home/edelivery/domibusf1/conf/domibus/domibus-
datasources.xml]: Cannot resolve reference to bean 'domibusJDBC-XADataSource' while setting bean
property 'dataSource'; nested exception is org.springframework.beans.factory.BeanCreationException: Error
creating bean with name 'domibusJDBC-XADataSource' defined in URL
[file:///home/edelivery/domibusf1/conf/domibus/domibus-datasources.xml]: Invocation of init method
failed; nested exception is com.atomikos.jdbc.AtomikosSQLException: The class
'com.mysql.jdbc.jdbc2.optional.MysqlXADataSource' specified by property 'xaDataSourceClassName' could
not be found in the classpath. Please make sure the spelling is correct, and that the required jar(s) are in the
classpath.

```

Solution: Add MySQL connector in **domibus/lib** folder.

14.6. Neither the JAVA_HOME nor the JRE_HOME environment variable is defined

| |
|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Neither the JAVA_HOME nor the JRE_HOME environment variable is defined At least one of these environment variables is needed to run this program |
|-----------------------------------------------------------------------------------------------------------------------------------------------------|

Solution: Set **JAVA_HOME** variable or/and **JRE_HOME**.

14.7. Cannot access Admin Console

```
http://your_server:your_port_number/domibus  
No SEVER errors in logs but no admin option in browser under
```

Solution: Check if the firewall is open for port_no (e.g. 8080).

14.8. Handshake Failure

Full stack trace below:

```
org.apache.cxf.interceptor.Fault: Could not write attachments.  
at org.apache.cxf.interceptor.AttachmentOutInterceptor.handleMessage(AttachmentOutInterceptor.java:74)  
at org.apache.cxf.phase.PhaseInterceptorChain.doIntercept(PhaseInterceptorChain.java:308)  
at org.apache.cxf.endpoint.ClientImpl.doInvoke(ClientImpl.java:514)  
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:423)  
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:324)  
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:277)  
at org.apache.cxf.endpoint.ClientImpl.invokeWrapped(ClientImpl.java:312)  
at org.apache.cxf.jaxws.DispatchImpl.invoke(DispatchImpl.java:327)  
at org.apache.cxf.jaxws.DispatchImpl.invoke(DispatchImpl.java:246)  
at eu.domibus.ebms3.sender.MSHDispatcher.dispatch(MSHDispatcher.java:126)  
at eu.domibus.ebms3.sender.MSHDispatcher$$FastClassBySpringCGLIB$$105974a1.invoke(<generated>)  
at org.springframework.cglib.proxy.MethodProxy.invoke(MethodProxy.java:204)  
at  
org.springframework.aop.framework.CglibAopProxy$CglibMethodInvocation.invokeJoinpoint(CglibAopProxy.java:717)  
at  
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:157)  
at  
org.springframework.transaction.interceptor.TransactionInterceptor$1.proceedWithInvocation(TransactionInterceptor.java:99)  
at  
org.springframework.transaction.interceptor.TransactionAspectSupport.invokeWithinTransaction(TransactionAspectSupport.java:281)  
at org.springframework.transaction.interceptor.TransactionInterceptor.invoke(TransactionInterceptor.java:96)  
at  
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:179)  
at  
org.springframework.aop.framework.CglibAopProxy$DynamicAdvisedInterceptor.intercept(CglibAopProxy.java:653)  
at eu.domibus.ebms3.sender.MSHDispatcher$$EnhancerBySpringCGLIB$$da53e95a.dispatch(<generated>)  
at eu.domibus.ebms3.sender.MessageSender.sendUserMessage(MessageSender.java:116)  
at eu.domibus.ebms3.sender.MessageSender.onMessage(MessageSender.java:195)  
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)  
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:57)  
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)  
at java.lang.reflect.Method.invoke(Method.java:606)  
at org.springframework.aop.support.AopUtils.invokeJoinpointUsingReflection(AopUtils.java:302)
```

```
at  
org.springframework.aop.framework.ReflectiveMethodInvocation.invokeJoinpoint(ReflectiveMethodInvocation.java:190)  
at  
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:157)  
at  
org.springframework.transaction.interceptor.TransactionInterceptor$1.proceedWithInvocation(TransactionInterceptor.java:99)  
at  
org.springframework.transaction.interceptor.TransactionAspectSupport.invokeWithinTransaction(TransactionAspectSupport.java:281)  
at org.springframework.transaction.interceptor.TransactionInterceptor.invoke(TransactionInterceptor.java:96)  
at  
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:179)  
at org.springframework.aop.framework.JdkDynamicAopProxy.invoke(JdkDynamicAopProxy.java:207)  
at com.sun.proxy.$Proxy163.onMessage(Unknown Source)  
at  
org.springframework.jms.listener.AbstractMessageListenerContainer.doInvokeListener(AbstractMessageListenerContainer.java:746)  
at  
org.springframework.jms.listener.AbstractMessageListenerContainer.invokeListener(AbstractMessageListenerContainer.java:684)  
at  
org.springframework.jms.listener.AbstractMessageListenerContainer.doExecuteListener(AbstractMessageListenerContainer.java:651)  
at  
org.springframework.jms.listener.AbstractPollingMessageListenerContainer.doReceiveAndExecute(AbstractPollingMessageListenerContainer.java:315)  
at  
org.springframework.jms.listener.AbstractPollingMessageListenerContainer.receiveAndExecute(AbstractPollingMessageListenerContainer.java:233)  
at  
org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.invokeListener(DefaultMessageListenerContainer.java:1150)  
at  
org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.executeOnGoingLoop(DefaultMessageListenerContainer.java:1142)  
at  
org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.run(DefaultMessageListenerContainer.java:1039)  
at java.lang.Thread.run(Thread.java:745)  
Caused by: javax.net.ssl.SSLHandshakeException: Received fatal alert: handshake_failure  
at sun.security.ssl.Alerts.getSSLEException(Alerts.java:192)  
at sun.security.ssl.Alerts.getSSLEException(Alerts.java:154)  
at sun.security.ssl.SSLSocketImpl.recvAlert(SSLSocketImpl.java:1979)  
at sun.security.ssl.SSLSocketImpl.readRecord(SSLSocketImpl.java:1086)  
at sun.security.ssl.SSLSocketImpl.performInitialHandshake(SSLSocketImpl.java:1332)  
at sun.security.ssl.SSLSocketImpl.startHandshake(SSLSocketImpl.java:1359)  
at sun.security.ssl.SSLSocketImpl.startHandshake(SSLSocketImpl.java:1343)  
at sun.net.www.protocol.https.HttpsClient.afterConnect(HttpsClient.java:563)  
at  
sun.net.www.protocol.https.AbstractDelegateHttpsURLConnection.connect(AbstractDelegateHttpsURLConnection.java:185)  
at sun.net.www.protocol.http.HttpURLConnection.getOutputStream(HttpURLConnection.java:1092)  
at sun.net.www.protocol.https.HttpsURLConnectionImpl.getOutputStream(HttpsURLConnectionImpl.java:250)
```

```

at
org.apache.cxf.transport.httpURLConnectionHTTPConduit$URLConnectionWrappedOutputStream.setupWrappedStream(URLConnectionHTTPConduit.java:236)
at
org.apache.cxf.transport.http.HTTPConduit$WrappedOutputStream.handleHeadersTrustCaching(HTTPConduit.java:1302)
at org.apache.cxf.transport.http.HTTPConduit$WrappedOutputStream.onFirstWrite(HTTPConduit.java:1262)
at
org.apache.cxf.transport.httpURLConnectionHTTPConduit$URLConnectionWrappedOutputStream.onFirstWrite(URLConnectionHTTPConduit.java:267)
at org.apache.cxf.io.AbstractWrappedOutputStream.write(AbstractWrappedOutputStream.java:47)
at org.apache.cxf.io.AbstractThresholdOutputStream.write(AbstractThresholdOutputStream.java:69)
at org.apache.cxf.io.AbstractWrappedOutputStream.write(AbstractWrappedOutputStream.java:60)
at org.apache.cxf.io.CacheAndWriteOutputStream.write(CacheAndWriteOutputStream.java:89)
at org.apache.cxf.attachment.AttachmentSerializer.writeProlog(AttachmentSerializer.java:172)
at org.apache.cxf.interceptor.AttachmentOutInterceptor.handleMessage(AttachmentOutInterceptor.java:72)
... 43 more

```

Solution: If you receive this error, then it's likely that you configured the client with TLSv1.1 while the server only accepts TLSv1.2.

Annex 1 - Usage of certificates in PEPPOL and OASIS_ for more information).

14.9. Message format for PEPPOL

When dynamic discovery is used, the "to" field should not be statically configured in the PMode (the "to" field may even be omitted in the message). The lookup is performed by C2 based on the **finalRecipient** message property.

Note: In Peppol, the service@type has a fixed value while the service@value is made of ProcessIdentifier@Scheme::ProcessIdentifier

Example of a message using the **finalRecipient** for dynamic discovery:

```

<ns:UserMessage>
  <ns:PartyInfo>
    <ns:From>
      <ns:PartyId type="urn:fdc:peppol.eu:2017:identifiers:ap">senderalias</ns:PartyId>
      <ns:Role>urn:fdc:peppol.eu:2017:roles:ap:as4</ns:Role>
    </ns:From>
    <ns:To>
      </ns:To>
    </ns:PartyInfo>
    <ns:CollaborationInfo>
      <ns:Service type=" urn:fdc:peppol.eu:2017:identifiers:proc-id">cenbii-procid-
      ubl:urn:www.cenbii.eu:profile:bii05:ver2.0</ns:Service>
      <ns:Action>urn:oasis:names:specification:ubl:schema:xsd:CreditNote-
      2::CreditNote##urn:www.cenbii.eu:transaction:biitrsn014:ver2.0:extended:urn:www.peppol.eu:bis:peppol5a:v
      er2.0::2.1</ns:Action>
    </ns:CollaborationInfo>
    <ns:MessageProperties>
      <ns:Property name="originalSender">urn:oasis:names:tc:ebcore:partyid-
      type:unregistered:C1</ns:Property>
      <ns:Property name="finalRecipient" type="iso6523-actorid-upis">0007:9340033829test1</ns:Property>
    </ns:MessageProperties>

```

```
</ns:UserMessage>
```

14.10. SMP entry

The following table describes the mapping between the PMode static configuration and the dynamic SMP records structure:

| SMP Endpoint registration record | PMode attributes |
|-----------------------------------------------------------------------------------------------|-------------------------------|
| ServiceMetadata/ServiceInformation/ProcessIdentifier | PMode[1].BusinessInfo.Service |
| ServiceMetadata/ServiceInformation/DocumentIdentifier | Pmode[1].BusinessInfo.Action |
| ServiceInformation/Processlist/Process/ServiceEndpointList/Endpoint/EndpointReference/Address | Pmode[].Protocol.Address |

Table 4 - SMP Entry Mapping

The Service Metadata Record also provides the receiving end's certificate. This certificate can be used to encrypt the message to be sent to the receiver. The certificate can also provide the name of the Access Point for this PMode by using the Certificate's CNAME as the PMode identifier (cf.[REF9]).

14.11. Domibus configuration for OASIS

To enable the integration with the SMP/SML components, Domibus requires some changes in the **domibus.properties** configuration file:

1. Add the following properties to enable the usage of the OASIS dynamic discovery client:
`domibus.dynamicdiscovery.client.specification"> OASIS`
Note: this property is not mandatory as it defaults to the above value.
2. Set the property "**domibus.smlzone**", e.g. "ehealth.acc.edelivery.tech.ec.europa.eu"

14.12. PMode configuration for OASIS

14.12.1. Sender PMode

In a dynamic discovery process, the receiver of the messages is not known beforehand and therefore the **PMode.Responder** parameter SHOULD NOT be set.

The dynamic discovery process must include a leg which maps the configured entry (action, service and service type – cf. 14.18 – "Message format for PEPPOL") of the Receiver in the SMP.

The security policy to be used in the leg is the policy that embeds the Binary Security Token into the security header (see section §5.1.1 – "Security Policies" for more information):

| |
|-----------------------------------|
| security="eDeliveryAS4Policy_BST" |
|-----------------------------------|

Sample Sender PMODE configuration extract:

```

...
<services>
    <service name="testService1"
        value="urn:www.cenbii.eu:profile:bi05:ver2.0"
        type="cenbii-procid-ubl"/>
</services>
<actions>
    <action name="tc1Action"
        value="your-schema-name'::urn:oasis:names:specification:ubl:schema:xsd:CreditNote-
2::CreditNote##urn:www.cenbii...."/>
</actions>
<securities>
    <security name="eDeliveryAS4Policy_BST"
        policy="eDeliveryAS4Policy_BST.xml"
        signatureMethod="RSA_SHA256"/>
</securities>
<legConfigurations>
    <legConfiguration name="pushTestcase1tc1Action"
        service="testService1"
        action="tc1Action"
        defaultMpc="defaultMpc"
        reliability="AS4Reliability"
        security="eDeliveryAS4Policy_BST"
        receptionAwareness="receptionAwareness"
        propertySet="eDeliveryPropertySet"
        payloadProfile="MessageProfile"
        errorHandling="demoErrorHandling"
        compressPayloads="true"/>
</legConfigurations>
<process name="tc1Process"
        agreement="agreementEmpty"
        mep="oneway"
        inding="push"
        initiatorRole="defaultInitiatorRole"
        responderRole="defaultResponderRole">
    <initiatorParties>
        <initiatorParty name="senderalias"/>
    </initiatorParties>
    <!-- no responderParties element -->
    <legs>
        <leg name="pushTestcase1tc1Action"/>
    </legs>
</process>
...

```

Remark:

Schema name should be added to action value. E.g: ehealth-actorid-qns::urn:oasis:names:specification:ubl:schema:xsd:CreditNote-2::CreditNote##urn:www.cenbii...

14.12.2. Receiver PMode

The dynamic discovery configuration of the receiver is similar to the configuration of the sender, except that the roles are swapped: the sender of the messages is not known beforehand. As a consequence, the **PMode.Initiator** parameter SHOULD NOT be set.

```
...
<process name="tc1Process"
    agreement="agreementEmpty"
    mep="oneway"
    inding="push"
    initiatorRole="defaultInitiatorRole"
    responderRole="defaultResponderRole">
    <responderParties>
        <responderParty name="receveralias"/>
    </responderParties>
    <!-- no initiatorParties element -->
    <legs>
        <leg name="pushTestcase1tc1Action"/>
    </legs>
</process>
...
```

14.13. Policy and certificates for OASIS

The receiver must include the certificate of the trusted authority(ies) in its truststore. It will only accept messages that were signed with certificates issued by the trusted authority(ies).

The sender truststore must include the SMP public certificate. This certificate is used by the AP to validate the identity of the used SMP (cf. §20 – ["Troubleshooting"](#)

[Failed to obtain DB connection from datasource](#)

SEVERE: Exception sending context initialized event to listener instance of class
org.springframework.web.context.ContextLoaderListener

```
org.springframework.beans.factory.BeanCreationException: Error creating bean with name
'org.springframework.scheduling.quartz.SchedulerFactoryBean#0' defined in ServletContext resource [/WEB-
INF/msh-config.xml]: Invocation of init method failed; nested exception is org.quartz.JobPersistenceException:
Failed to obtain DB connection from datasource
'springTxDataSource.org.springframework.scheduling.quartz.SchedulerFactoryBean#0':
com.atomikos.jdbc.AtomikosSQLException: Failed to grow the connection pool [See nested exception:
com.atomikos.jdbc.AtomikosSQLException: Failed to grow the connection pool]
    at
org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.initializeBean(AbstractAuto-
wireCapableBeanFactory.java:1578)
    at
org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.doCreateBean(AbstractAuto-
wireCapableBeanFactory.java:545)
    at
org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.createBean(AbstractAutowi-
reCapableBeanFactory.java:482)
    at
org.springframework.beans.factory.support.AbstractBeanFactory$1.getObject(AbstractBeanFactory.java:305)
```

```

at
org.springframework.beans.factory.support.DefaultSingletonBeanRegistry.getSingleton(DefaultSingletonBeanR
egistry.java:230)
at
org.springframework.beans.factory.support.AbstractBeanFactory doGetBean(AbstractBeanFactory.java:301)
SEVERE: One or more listeners failed to start. Full details will be found in the appropriate container log file
May 11, 2016 10:12:43 AM org.apache.catalina.util.SessionIdGeneratorBase createSecureRandom
INFO: Creation of SecureRandom instance for session ID generation using [SHA1PRNG] took [13,256]
milliseconds.
May 11, 2016 10:12:43 AM org.apache.catalina.core.StandardContext startInternal
SEVERE: Context [/domibus] startup failed due to previous errors
May 11, 2016 10:12:43 AM org.apache.catalina.core.ApplicationContext log
INFO: Closing Spring root WebApplicationContext
May 11, 2016 10:12:43 AM org.apache.catalina.core.ApplicationContext log
INFO: Shutting down log4j

```

Solution: Setup the password properly in the **domibus.properties**.

14.14. Exception sending context initialized event to listener instance of class

```

SEVERE: Exception sending context initialized event to listener instance of class
org.springframework.web.context.ContextLoaderListener
org.springframework.beans.factory.BeanCreationException: Error creating bean with name
'entityManagerFactory' defined in URL [file:///home/edelivery/domibusf1/conf/domibus/domibus-
datasources.xml]: Cannot resolve reference to bean 'domibusJDBC-XADataSource' while setting bean
property 'dataSource'; nested exception is org.springframework.beans.factory.BeanCreationException: Error
creating bean with name 'domibusJDBC-XADataSource' defined in URL
[file:///home/edelivery/domibusf1/conf/domibus/domibus-datasources.xml]: Invocation of init method
failed; nested exception is com.atomikos.jdbc.AtomikosSQLException: The class
'com.mysql.jdbc.jdbc2.optional.MysqlXADataSource' specified by property 'xaDataSourceClassName' could
not be found in the classpath. Please make sure the spelling is correct, and that the required jar(s) are in the
classpath.

```

Solution: Add MySQL connector in domibus/lib folder.

14.15. Neither the JAVA_HOME nor the JRE_HOME environment variable is defined

Neither the JAVA_HOME nor the JRE_HOME environment variable is defined
At least one of these environment variables is needed to run this program

Solution: Set JAVA_HOME variable or/and JRE_HOME.

14.16. Cannot access Admin Console

http://your_server:your_port_number/domibus
No SEVER errors in logs but no admin option in browser under

Solution: Check if the firewall is open for port_no (e.g. 8080).

14.17. Handshake Failure

Full stack trace below:

```
org.apache.cxf.interceptor.Fault: Could not write attachments.
at org.apache.cxf.interceptor.AttachmentOutInterceptor.handleMessage(AttachmentOutInterceptor.java:74)
at org.apache.cxf.phase.PhaseInterceptorChain.doIntercept(PhaseInterceptorChain.java:308)
at org.apache.cxf.endpoint.ClientImpl.doInvoke(ClientImpl.java:514)
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:423)
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:324)
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:277)
at org.apache.cxf.endpoint.ClientImpl.invokeWrapped(ClientImpl.java:312)
at org.apache.cxf.jaxws.DispatchImpl.invoke(DispatchImpl.java:327)
at org.apache.cxf.jaxws.DispatchImpl.invoke(DispatchImpl.java:246)
at eu.domibus.ebms3.sender.MSHDispatcher.dispatch(MSHDispatcher.java:126)
at eu.domibus.ebms3.sender.MSHDispatcher$$FastClassBySpringCGLIB$$105974a1.invoke(<generated>)
at org.springframework.cglib.proxy.MethodProxy.invoke(MethodProxy.java:204)
at
org.springframework.aop.framework.CglibAopProxy$CglibMethodInvocation.invokeJoinpoint(CglibAopProxy.java:717)
at
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:157)
at
org.springframework.transaction.interceptor.TransactionInterceptor$1.proceedWithInvocation(TransactionInterceptor.java:99)
at
org.springframework.transaction.interceptor.TransactionAspectSupport.invokeWithinTransaction(TransactionAspectSupport.java:281)
at org.springframework.transaction.interceptor.TransactionInterceptor.invoke(TransactionInterceptor.java:96)
at
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:179)
at
org.springframework.aop.framework.CglibAopProxy$DynamicAdvisedInterceptor.intercept(CglibAopProxy.java:653)
at eu.domibus.ebms3.sender.MSHDispatcher$$EnhancerBySpringCGLIB$$da53e95a.dispatch(<generated>)
at eu.domibus.ebms3.sender.MessageSender.sendUserMessage(MessageSender.java:116)
at eu.domibus.ebms3.sender.MessageSender.onMessage(MessageSender.java:195)
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:57)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:606)
at org.springframework.aop.support.AopUtils.invokeJoinpointUsingReflection(AopUtils.java:302)
at
org.springframework.aop.framework.ReflectiveMethodInvocation.invokeJoinpoint(ReflectiveMethodInvocation.java:190)
at
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:157)
at
org.springframework.transaction.interceptor.TransactionInterceptor$1.proceedWithInvocation(TransactionInterceptor.java:99)
```

```
at  
org.springframework.transaction.interceptor.TransactionAspectSupport.invokeWithinTransaction(TransactionAspectSupport.java:281)  
at org.springframework.transaction.interceptor.TransactionInterceptor.invoke(TransactionInterceptor.java:96)  
at  
org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:179)  
at org.springframework.aop.framework.JdkDynamicAopProxy.invoke(JdkDynamicAopProxy.java:207)  
at com.sun.proxy.$Proxy163.onMessage(Unknown Source)  
at  
org.springframework.jms.listener.AbstractMessageListenerContainer.invokeListener(AbstractMessageListenerContainer.java:746)  
at  
org.springframework.jms.listener.AbstractMessageListenerContainer.invokeListener(AbstractMessageListenerContainer.java:684)  
at  
org.springframework.jms.listener.AbstractMessageListenerContainer.doExecuteListener(AbstractMessageListenerContainer.java:651)  
at  
org.springframework.jms.listener.AbstractPollingMessageListenerContainer.doReceiveAndExecute(AbstractPollingMessageListenerContainer.java:315)  
at  
org.springframework.jms.listener.AbstractPollingMessageListenerContainer.receiveAndExecute(AbstractPollingMessageListenerContainer.java:233)  
at  
org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.invokeListener(DefaultMessageListenerContainer.java:1150)  
at  
org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.executeOnGoingLoop(DefaultMessageListenerContainer.java:1142)  
at  
org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.run(DefaultMessageListenerContainer.java:1039)  
at java.lang.Thread.run(Thread.java:745)  
Caused by: javax.net.ssl.SSLHandshakeException: Received fatal alert: handshake_failure  
at sun.security.ssl Alerts.getSSLEException(Alerts.java:192)  
at sun.security.ssl Alerts.getSSLEException(Alerts.java:154)  
at sun.security.ssl SSLSocketImpl.recvAlert(SSLSocketImpl.java:1979)  
at sun.security.ssl SSLSocketImpl.readRecord(SSLSocketImpl.java:1086)  
at sun.security.ssl SSLSocketImpl.performInitialHandshake(SSLSocketImpl.java:1332)  
at sun.security.ssl SSLSocketImpl.startHandshake(SSLSocketImpl.java:1359)  
at sun.security.ssl SSLSocketImpl.startHandshake(SSLSocketImpl.java:1343)  
at sun.net.www.protocol.https.HttpsClient.afterConnect(HttpsClient.java:563)  
at  
sun.net.www.protocol.https.AbstractDelegateHttpsURLConnection.connect(AbstractDelegateHttpsURLConnection.java:185)  
at sun.net.www.protocol.http.HttpURLConnection.getOutputStream(HttpURLConnection.java:1092)  
at sun.net.www.protocol.https.HttpsURLConnectionImpl.getOutputStream(HttpsURLConnectionImpl.java:250)  
at  
org.apache.cxf.transport.http.URLConnectionHTTPConduit$URLConnectionWrappedOutputStream.setupWrappedStream(URLConnectionHTTPConduit.java:236)  
at  
org.apache.cxf.transport.http.HTTPConduit$WrappedOutputStream.handleHeadersTrustCaching(HTTPConduit.java:1302)  
at org.apache.cxf.transport.http.HTTPConduit$WrappedOutputStream.onFirstWrite(HTTPConduit.java:1262)  
at  
org.apache.cxf.transport.http.URLConnectionHTTPConduit$URLConnectionWrappedOutputStream.onFirstWrite(URLConnectionHTTPConduit.java:267)
```

```

at org.apache.cxf.io.AbstractWrappedOutputStream.write(AbstractWrappedOutputStream.java:47)
at org.apache.cxf.io.AbstractThresholdOutputStream.write(AbstractThresholdOutputStream.java:69)
at org.apache.cxf.io.AbstractWrappedOutputStream.write(AbstractWrappedOutputStream.java:60)
at org.apache.cxf.io.CacheAndWriteOutputStream.write(CacheAndWriteOutputStream.java:89)
at org.apache.cxf.attachment.AttachmentSerializer.writeProlog(AttachmentSerializer.java:172)
at org.apache.cxf.interceptor.AttachmentOutInterceptor.handleMessage(AttachmentOutInterceptor.java:72)
... 43 more

```

Solution: If you receive this error, then it's likely that you configured the client with TLSv1.1 while the server only accepts TLSv1.2.

Annex 1 - Usage of certificates in PEPPOL and OASIS [for more information](#)).

14.18. Message format for OASIS

When dynamic discovery is used, the "to" field should not be statically configured in the PMode (the "to" field may even be omitted in the message). The lookup is performed by C2 based on the **finalRecipient** message property.

Note 1: For OASIS clients; in the PMode "action" value, the document scheme must be included with the document ID (for PEPPOL client, only document ID is needed).

Note 2: For OASIS clients; the value of the "service@type" must be set to the "processIdentifier@scheme".

Example of message using the **finalRecipient** for dynamic discovery:

```

<ns:UserMessage>
  <ns:PartyInfo>
    <ns:From>
      <ns:PartyId type="urn:oasis:names:tc:ebcore:partyid-type:unregistered">senderalias</ns:PartyId>
      <ns:Role>http://docs.oasis-open.org/ebxml-msg/ebms/v3.0/ns/core/200704/initiator</ns:Role>
    </ns:From>
    <ns:To>
    </ns:To>
  </ns:PartyInfo>
  <ns:CollaborationInfo>
    <ns:Service type="cenbii-procid-ubl">urn:www.cenbii.eu:profile:bi05:ver2.0</ns:Service>
      <ns:Action>'your_schema_name'::urn:oasis:names:specification:ubl:schema:xsd:CreditNote-2::CreditNote##urn:www.cenbii.eu:transaction:biitrns014:ver2.0:extended:urn:www.peppol.eu:bis:peppol5a:ver2.0::2.1</ns:Action>
    </ns:CollaborationInfo>
    <ns:MessageProperties>
      <ns:Property name="originalSender">urn:oasis:names:tc:ebcore:partyid-type:unregistered:C1</ns:Property>
      <ns:Property name="finalRecipient" type="iso6523-actorid-upis">0007:9340033829test1</ns:Property>
    </ns:MessageProperties>
  </ns:UserMessage>

```

15. MESSAGE PULLING

15.1. Setup

In order to configure message pulling the process section should be configured with **mep** set to "oneway" and binding set to "pull" as shown in the following example:

```
<process name="tc1Process"
    agreement="agreementEmpty"
    mep="oneway"
    binding="pull"
    initiatorRole="defaultInitiatorRole"
    responderRole="defaultResponderRole">
    <initiatorParties>
        <initiatorParty name="initiatoralias"/>
    </initiatorParties >
    <responderParties>
        <responderParty name="receiveralias"/>
    </responderParties>
    <!-- no initiatorParties element -->
    <legs>
        <leg name="pushTestcase1tc1Action"/>
    </legs>
</process>
```

In the case of a pull process, the **initiatorParties** section contains the party that initiate the pull request. The **responderParties** section contains the parties that can be pulled from.

In domibus.properties configuration file adapt the following properties to your needs. Note that domibus.msh.pull.cron and domibus.pull.queue.concurrency are mandatory.

```
# ----- Pulling-----
#Cron expression used for configuring the message puller scheduling.
domibus.msh.pull.cron=0 0 0/1 * * ?

# Number of threads used to parallelize the pull requests.
domibus.pull.queue.concurrency=1-1

#Number of pull requests executed every cron cycle
#domibus.pull.request.send.per.job.cycle=1
```

15.2. Configuration restriction

A correctly configured **one-way pull process** should only contain one party configured in the **initiatorParties** section.

Different **legConfiguration** with the same **defaultMpc** (highlighted in red in the following configuration) should not be configured in the same pull process or across different pull processes.

If those restrictions are not respected, the message will not be exchanged and a warning message will detail the configuration problem.

```
<legConfiguration name="pushTestcase1tc2Action"
    service="testService1"
    action="tc2Action"
    defaultMpc="defaultMpc"
    reliability="AS4Reliability"
    security="eDeliveryAs4Policy"
    receptionAwareness="receptionAwareness"
    errorHandling="demoErrorHandling"
    propertySet="eDeliveryPropertySet"
    payloadProfile="MessageProfile"
    compressPayloads="true"/>
```

16. MULTI-TENANCY

Domibus supports multiple domains (configurations) configured in one Domibus instance. This means that each domain has its own configuration (PMode, keystore, truststore and Domibus properties, etc). These multiple configurations allow one Domibus instance to process messages from multiple domains simultaneously.

Domibus uses **Schema per tenant** strategy to implement multi-tenancy, meaning that the data associated to a domain will be saved in a database schema dedicated to the domain.

16.1. Configuration

By default multi-tenancy is not activated. In order to activate multi-tenancy the following property that defines the general schema needs to be configured in **domibus.properties**:

```
domibus.database.general_schema =general_schema
```

The general_schema needs to be initialized using the distributed database script **mysql5innoDB-x.y.z-multi-tenancy.ddl** or **oracle10g-x.y.z-multi-tenancy.ddl**.

Additional domains can be created by adding domain configuration files under **cef_edelivery_path/conf/domibus** directory. The domain configuration file needs to be configured according to the domain name, so the keystore, truststore, etc need to be configured. The domain configuration file has to respect the following convention:

```
domain_name-domibus.properties
```

where **domain_name** is the name of the domain.

Each domain uses its own dedicated schema which is configured in the domain configuration file. The database user that is used to connect to the **general_schema** schema needs to have the necessary privileges so that it can access the database schemas for all the configured domains.

The domain database schema needs to be initialized using the distributed database script **mysql5innoDB-x.y.z.ddl** or **mysql5innoDB-x.y.z.ddl**. Please note that the database script **mysql5innoDB-x.y.z-data.ddl** or **mysql5innoDB-x.y.z-data.ddl** do not have to be executed in multi-tenancy mode.

Once multi-tenancy is activated and with no other additional configuration, Domibus will use the domain named **default** for the incoming and outgoing messages. The domain **default** is configured in **domibus.properties**.

More information on how multi-tenancy is implemented can be found in the **Domibus Software Architecture Document** (c.f. [REF11]).

16.1.1. Tomcat Configuration

The Domibus database in Tomcat is configured in **domibus.properties** file and for running Domibus in multi-tenancy mode the database related properties need to be adapted.

Please find below an example of the database properties that need to be configured for multi-tenancy:

```
domibus.database.general.schema=general_schema

# optional property used in case the default domain is used
domibus.database.schema=domibus

domibus.datasource.xa.property.url=jdbc:mysql://${domibus.database.serverName}:${domibus.database.port}/${domibus.database.general.schema}?pinGlobalTxToPhysicalConnection=true

domibus.datasource.url=jdbc:mysql://${domibus.database.serverName}:${domibus.database.port}/${domibus.database.general.schema }?useSSL=false
```

16.1.2. WebLogic and WildFly Configuration

Most of the database configuration for WebLogic and WildFly is done in the application server. The datasources configured in the application server need to be configured with the user and password that connects to the **general_schema** schema. At runtime the database schema will be changed based on the current domain.

Please find below an example of the database properties that need to be configured for multi-tenancy:

```
domibus.database.general.schema=general_schema

# optional property used in case the default domain is used
domibus.database.schema=domibus
```

16.2. Domain Properties

The following properties listed in the table are used to configure a domain. Some properties are defaulting to the properties defined in **domibus.properties** if they are not defined in the domain properties file. All the properties defined in a domain property file(e.g. **domain_name-domibus.properties**) need to be prefixed by the domain name.

Example:

1. If the domain name is **digit**, the property file **digit-domibus.properties** is used to configure the **digit** domain.
2. Defining a property named **digit.domibus.msh.messageid.suffix** will override the property **domibus.msh.messageid.suffix** defined in **domibus.properties**.

| Domain configuration Property | Defaults to domibus.properties if not defined |
|-------------------------------------------------|------------------------------------------------------|
| <i>domain_name.domibus.msh.messageid.suffix</i> | yes |

| | |
|------------------------------------------------------------------------|-----|
| <i>domain_name</i> .domibus.msh.retry.cron | yes |
| <i>domain_name</i> .domibus.smlzone | yes |
| domibus.dynamicdiscovery.client.specification | yes |
| domibus.dynamicdiscovery.peppolclient.mode | yes |
| domibus.dynamicdiscovery.oasisclient.regexCertificateSubjectValidation | yes |
| domibus.dynamicdiscovery.partyid.responder.role | yes |
| domibus.dynamicdiscovery.partyid.type | yes |
| domibus.dispatcher.allowChunking | yes |
| domibus.dispatcher.chunkingThreshold | yes |
| domibus.dispatcher.concurrency | yes |
| domibus.msh.pull.cron | yes |
| domibus.retentionWorker.cronExpression | yes |
| message.retention.downloaded.max.delete | yes |
| message.retention.not_downloaded.max.delete | yes |
| domibus.sendMessage.messageIdPattern | yes |
| domibus.dispatcher.connectionTimeout | yes |
| domibus.dispatcher.receiveTimeout | yes |
| domibus.msh.retry.tolerance | yes |

| | |
|---------------------------------------------------|-----|
| domibus.security.keystore.location | no |
| domibus.security.keystore.type | no |
| domibus.security.keystore.password | no |
| domibus.security.key.private.alias | no |
| domibus.security.key.private.password | no |
| domibus.security.truststore.location | no |
| domibus.security.truststore.type | no |
| domibus.security.truststore.password | no |
| domibus.receiver.certificate.validation.onsending | yes |
| domibus.sender.certificate.validation.onsending | yes |
| domibus.sender.certificate.validation.onreceiving | yes |
| domibus.sender.trust.validation.onreceiving | yes |

16.3. Logging

Domibus logs into 3 log files when running in non multi-tenancy mode (**domibus.log**, **domibus-business.log** and **domibus-security.log**) that are configured in **logback.xml** file. More information about what is being logged into those files can be found in section [9.3 - Application Logging](#).

When running in multi-tenancy mode, the Domibus log configuration file **logback.xml** has to be modified in order to include the log configuration for each domain. This is necessary to segregate the log statements per domain, each domain having its own set of the 3 logs files mentioned above.

In order to configure the logs per domain please follow the steps:

1. Customize the **default-logback.xml** file distributed in each server configuration archive.
 - a. Rename the **default-logback.xml** file according to the domain name. Eg: If the domain name is **domain1** the file should be renamed to **domain1-logback.xml**

- b. Adapt the value of the **domainName** variable defined in the domain logback configuration file. The value should correspond with the name of the configured domain.

```
<included>
<property name="domainName" value="domain1" scope="local" />
```

2. Include the domain configuration file into the main **logback.xml** file

```
<configuration>
  <!-- start include domains config files here -->
  <include optional="true" file="${catalina.home}/conf/domibus/domain1-logback.xml"/>
```

16.4. Plugins

When running in multi-tenancy mode the plugins security is activated by default, no matter if the property **domibus.auth.unsecureLoginAllowed** is set to true. This is needed in order to identify the request performed by the user and associate it to a specific domain. As a result every request sent to Domibus need to be authenticated.

Please note that the **Default JMS Plugin** require the creation of additional JMS queues. More info on which queues need to be created can be found in the **JMS Plugin ICD** document (see [REF12]).

More information on this topic can be found in the **Domibus Software Architecture Document** (c.f. [REF11]).

16.5. Users

In multi-tenancy mode there is a new user named **super** which has the privileges to access all the available domains. The default password for the **super** user is **123456**.

The first time a new domain is created, the **super** user creates a new user in the **Domibus Administration Console** with role **ROLE_ADMIN** associated to the newly created domain. More details how to create users can be found in the help page of the **Users** page.

Then the **super** user sends the credentials to the domain admin user. The domain admin logs into the **Domibus Administration Console** using the received credentials and has to change its password in the **Users** page. The domain admin has access only to his domain and he has the privileges to create new users associated to domain.

17. TEST SERVICE

This section describes how to configure and test the communication between two Access Points. This feature allows communication partners to perform a basic test of the communication configuration (including security at network, transport and message layer, and reliability) in any environment, including the production environment.

Domibus offers a page in the Administration Console which gives the possibility to inspect and send **Test** messages to other Access Points.

The information about both messages can be seen in the **Test Service** screen and, every time “Receiver Party Id” changes, you are able to check the updated information of Last Sent and Last Received **Test** Messages.

17.1. Test Service Configuration

In order to configure the **Test Service**, the PMode needs to contain the the correct configuration for sending **Test** messages.

Note: The Domibus sample PModes contain already the configuration for the **Test Service**

```
<services>
  ...
  <service name="testService" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/service"/>
</services>
<actions>
  ...
  <action name="testAction" value="http://docs.oasis-open.org/ebxml-
msg/ebms/v3.0/ns/core/200704/test"/>
</actions>

<legConfigurations>
  ...
  <legConfiguration name="testServiceCase">
```

```
        service="testService"
        action="testAction"
        defaultMpc="defaultMpc"
        reliability="AS4Reliability"
        security="eDeliveryAS4Policy"
        receptionAwareness="receptionAwareness"
        propertySet="eDeliveryPropertySet"
        payloadProfile="MessageProfile"
        errorHandling="demoErrorHandling"
        compressPayloads="true"/>

</legConfigurations>
```

18. ALERT FEATURE

18.1. Description

The purpose of the alert feature is to use different available media to notify the Domibus administrator in case of unusual behaviour. Those notifications are presented to the Domibus administrator under the form of configurable alerts. The alerts can be browsed in the **Domibus Admin Console** and received by **email**.

Currently, only email notification channel is available, but other communication media will be added in future releases.

Three topics are available for monitoring: Message status change, authentication issues and certificate expiration.

18.2. Main configuration

The properties, described below, can be configured in the domibus.properties configuration file.

By default, alerts are not activated. A single property can activate or deactivate the entire alert concept. In order to activate it, the following property should be set to true.

```
# ----- Alert management -----
#enable/disable the entire alert module. Pay attention to the fact that if the module is activated, all properties
#under the mandatory section should be configured.
domibus.alert.active=true
```

Once the alerts are activated, the SMTP server needs also to be configured. In such case the following properties are mandatory:

```
# -----Mandatory configuration start (if domibus.alert.active=true) -----
#Smtp sever url for sending alert
#domibus.alert.sender.smtp.url=

#Smtp sever port
#domibus.alert.sender.smtp.port=

#Smtp sever user
#domibus.alert.sender.smtp.user=

#Smtp sever user password
#domibus.alert.sender.smtp.password=

#Alert sender email
#domibus.alert.sender.email=

#Alert email receiver.
#domibus.alert.receiver.email=
```

The first four properties are used to configure respectively, the URL, the port, the user and the password to authenticate to the SMTP server. In case of multi-tenancy configuration, those four properties should be configured in the main domibus.properties. Indeed only one SMTP server can be configured for all the tenants.

The last two properties are needed to respectively set the emails of the alert sender and the alert receiver. In case of multi-tenancy configuration, those two properties must be configured in each domain configuration file.

The following properties are already preconfigured with default values and therefore are not mandatory to be configured:

```
#The following properties can stay commented if not modifications to the default values are needed.

#Cron configuration for cleaning alerts.
#domibus.alert.cleaner.cron=0 0 0/1 * * ?

# Alerts lifetime in days of before cleaning.
#domibus.alert.cleaner.alert.lifetime=20

#Concurrency to process the alerts.
#domibus.alert.queue.concurrency=1

#Frequency of failed alerts retry.
#domibus.alert.retry.cron=0 0/1 * * * ?

#Elapsed time in minute between alert retry.
#domibus.alert.retry.time=1

#Number of retry for failed alerts.
#domibus.alert.retry.max_attempts=2
```

By default, Domibus will check every hour for expired alerts. The default lifetime for an alert is 20 days after which the alert is deleted from the system.

The concurrency property allows processing multiple alerts in parallel. Alerts can be configured with a retry in case of dispatch failure. By default Domibus will wait one minute between two alert dispatch retry, and it will retry twice.

18.3. Message status change alerts

Domibus is able to track Message status changes. Some attention should be paid to avoid configuring the status of frequently changing statuses (e.g.: From SEND_ENQUEUED to ACKNOWLEDGE) in order not be spammed. Nevertheless it is possible to track all status changes.

Each alert topic (Message status change, authentication and certificate expiration) can be activated or deactivated independently from the others. In order to work, the main alert module should always be activated though. (See previous section).

By default, message status change alerts are not activated. In order to activate them, the following property should be set to true.

```
# ----- Alert management:messaging module -----
#enable/disable the messaging alert module.
domibus.alert.msg.communication_failure.active=true
```

The following properties are already preconfigured with default values and therefore are not mandatory to be configured:

```
#Message status change that should be notified by the messaging alert module. Comma separated.
#domibus.alert.msg.communication_failure.states=SEND_FAILURE

#Alert levels corresponding to message status defined in previous
property(domibus.alert.msg.communication_failure.states) . Should be (HIGH, MEDIUM or LOW)
#domibus.alert.msg.communication_failure.level=HIGH

#Messaging alert module mail subject.
#domibus.alert.msg.communication_failure.mail.subject=Message status change
```

Per default, Domibus will only track message status change to SEND_FAILURE. The level of the alert that will be trigger is HIGH. The last property allows configuring the subject of the mail sent.

If there is a need to track another message status change, a comma separated list can be configured.

```
Eg: domibus.alert.msg.communication_failure.states=SEND_FAILURE,ACKNOWLEDGED
```

If there is a need to set an alert level per status change it can be done as well with a comma separated list.

```
domibus.alert.msg.communication_failure.level=HIGH,LOW
```

In the preceding scenario, an alert for a message being set in send_failure status will have a high level and an alert for a message being set in acknowledged status will have a low level.

18.4. Authentication Alerts

Domibus is able to track admin console login failure and user account disabling. The login failure alert will occur on each incorrect tentative. Note that if the username encoded is unknown to the system, no alert will be created. Only known user with invalid password will be tracked. The account disabled alert will occur either because the user did too much invalid login attempts or because an administrator disabled the account.

By default, login failure alerts are not activated. In order to activate them, the following property should be set to true.

```
# ----- Alert management: Authentication module -----
#Enable/disable the login failure alert of the authentication module.
domibus.alert.user.login_failure.active=true
```

The following properties are already preconfigured with default values and therefore are not mandatory to configure:

```
#Alert level for login failure.
#domibus.alert.user.login_failure.level=LOW

#Login failure mail subject.
#domibus.alert.user.login_failure.mail.subject=Login failure
```

Per default, the alert level for a login failure is low. The last property allows configuring the subject of the mail sent.

By default, account disabled alerts are not activated. In order to activate them, the following property should be set to true.

```
#Enable/disable the account disable alert of the authentication module.
domibus.alert.user.account_disabled.active=true
```

The following properties are already preconfigured with default values and therefore are not mandatory to configure:

```
#Alert level for account disabled.
#domibus.alert.user.account_disabled.level=HIGH

#When should the account disabled alert be triggered.
# 2 possible values:
# AT_LOGON: An alert will be triggered each time a user tries to login to a disabled account.
# WHEN_BLOCKED: An alert will be triggered once when the account got disabled.
#domibus.alert.user.account_disabled.moment=WHEN_BLOCKED

#Account disabled mail subject.
#domibus.alert.user.account_disabled.subject=Account disabled
```

Per default, the alert level for an account disabled is high. The next property specifies when an account_disabled alert should be triggered. It can be only at disabling time or at every new login attempt after the account has been disabled. The default value WHEN_BLOCKED will therefore create only one alert when the account is disabled.

The last property allows configuring the subject of the mail sent.

18.5. Certificate scanner alerts

Domibus is able to track certificate expiration and imminent expiration. Obviously the certificate expired alert occurs when a certificate expires. The number of days the alert should be triggered after the expiration is configurable. The imminent expiration alert occurs a certain time before the certificate expiration. The number of days the alert should be triggered before expiration is configurable. The alert frequency for both trackers can be configured.

By default, imminent certificate expiration alerts are not activated. In order to activate them, the following property should be set to true.

```
# ----- Alert management: Certificate scanner -----  
  
#Enable/disable the imminent certificate expiration alert of certificate scanner module.  
domibus.alert.cert.imminent_expiration.active=true
```

The following properties are already preconfigured with default values and therefore are not mandatory to configure:

```
#Number of days before revocation as from when the system should start sending alerts.  
#domibus.alert.cert.imminent_expiration.delay_days=61  
  
#Frequency in days between alerts.  
#domibus.alert.cert.imminent_expiration.frequency_days=14  
  
#Certificate imminent expiration alert level.  
#domibus.alert.cert.imminent_expiration.level=HIGH  
  
#Certificate imminent expiration mail subject.  
#domibus.alert.cert.imminent_expiration.mail.subject=Certificate imminent expiration
```

Per default, Domibus will send certificate imminent expiration alerts 61 days before the expiration. It will send alerts at a pace of one alert every 14 days. The level of the alert will be HIGH. The last property allows configuring the subject of the mail sent.

By default, certificate expired alerts are not activated. In order to activate them, the following property should be set to true.

```
#Enable/disable the certificate expired alert of certificate scanner module.  
domibus.alert.cert.expired.active=true
```

The following properties are already preconfigured with default values and therefore are not mandatory to configure.

```
#Frequency in days between alerts.  
#domibus.alert.cert.expired.frequency_days=7  
  
#How long(in days) after the revocation should the system trigger alert for the expired certificate.  
#domibus.alert.cert.expired.duration_days=92  
  
#Certificate expired alert level.  
#domibus.alert.cert.expired.level=HIGH
```

```
#Certificate expired mail subject.  
#domibus.alert.cert.expired.mail.subject=Certificate expired
```

Per default, Domibus will send certificate expired alerts during 92 days after the expiration. It will send alerts at a pace of one alert every 7 days. The level of the alert will be HIGH. The last property allows configuring the subject of the mail sent.

19. OPERATIONAL GUIDELINES

In this section you will find some recommendations on how to administer Domibus in an efficient way. The following topics are tackled: JMS Queue management, log management, capacity planning, database management and the monitoring of message life cycle.

19.1. JMS Queue Management

Domibus provides following out of the box features to manage the JMS Queues used in Domibus (see also §9.4- Queue Monitoring):

- Inspecting and filtering the messages from a queue based on the contents of Source, Period, JMS Type or Selector
- Move message from the DLQ (Dead Letter Queue) to the original Queue
- Delete stuck or pending message(s) from Queues

It is recommended to monitor the Queue size and number of messages in the different Queues. If some messages are stuck in any of the Queue then alerts must be sent to the Domibus Administrator.

Please pay special attention to the deadletter queue (DLQ). Messages stuck in this queue is a signal that there is some issue in Domibus that needs to be analysed and an alert should be sent to the Domibus Administrator.

Important:

The ‘ListPendingMessages’ operation on WS Plugin browses the JMS queue. Max count is limited to destination MaxBrowsePageSize which can be changed via the ‘domibus.listPendingMessages.maxCount’ Domibus property.

If your received messages are not returned by the webservice listPendingMessages method the you should:

1. increase the value of the ‘domibus.listPendingMessages.maxCount’ property;
2. delete the messages from the domibus.notification.webservice queue with selector NOTIFICATION_TYPE=MESSAGE_SEND_SUCCESS using JMX tools :
<http://activemq.apache.org/how-can-i-monitor-activemq.html> .

19.2. Log Management

19.2.1. Log Level

It is recommended that the log level is correctly set in all the environments:

- The log level should be set to INFO/DEBUG in all the test environments for de-bugging purpose.
- The log level should be set to ERROR/WARN in production environment (keeping log level to INFO in production environment will degrade the performance of Domibus).

19.2.2. Log Rotation and Archiving

It is recommended that log rotation and archiving logic is implemented.

Domibus provides by default log rotation, but Domibus administrator should manage Domibus archiving logic.

19.2.3. Log Monitoring

It is recommended to monitor continuously Domibus logs. It can be done using an automated script which looks for keywords like "ERROR", "WARNING", etc. and reports all the errors and warnings to the Domibus administrator.

19.3. Capacity Planning

19.3.1. JVM Memory Management

Hereafter some recommendations:

- the JVM memory parameters must first be tested in a test environment with the load expected in production
- the JVM parameters i.e. heap size must be monitored with the help of automated scripts and any abnormal hikes in heap size must be reported to the administrator.

19.3.2. CPU, IO operations and Disk Space Monitoring

CPU, IO operations and disk space must be continuously monitored using automated scripts. Any abnormal hikes must be reported to Domibus administrator and further investigated.

19.4. Database Management

19.4.1. Database Monitoring

It is important to monitor the database size.

The Payload of the message is deleted from the sending Access Point. Only the metadata of the message stays in the table. The Payload from the receiving Access Point is deleted based on the retention policy defined in the Pmode settings.

Domibus uses approximately 40 MB of table space to store the metadata of 1000 messages.

19.4.2. Database Archiving

Since the Database contains AS4 receipts that are used for non-repudiation purposes, they should be archived before purging the database.

The metadata of the database can be purged if it is no longer required.

19.4.3. Monitor Message Life Cycle

It is recommended to monitor the message status in the TB_MessageLog table. Automated scripts can be used to count different status in the table.

Please pay special attention to the following statuses:

- WAITING_FOR_RETRY: this means that there is some issue between C2 and C3 that must be resolved.
- SEND_FAILURE: this means that there is some issue between C2 and C3 that must be resolved.
- SEND_ENQUEUED: this message status is part of the successful message life cycle, however abnormal increase in the count of messages with this status means that there is an issue. Further investigation is recommended.

20. TROUBLESHOOTING

20.1. Failed to obtain DB connection from datasource

```
SEVERE: Exception sending context initialized event to listener instance of class org.springframework.web.context.ContextLoaderListener
org.springframework.beans.factory.BeanCreationException: Error creating bean with name 'org.springframework.scheduling.quartz.SchedulerFactoryBean#0' defined in
ServletContext resource [/WEB-INF/msh-config.xml]: Invocation of init method failed; nested exception is org.quartz.JobPersistenceException: Failed to obtain DB connection
from datasource 'springTxDataSource.org.springframework.scheduling.quartz.SchedulerFactoryBean#0': com.atomikos.jdbc.AtomikosSQLException: Failed to grow the
connection pool [See nested exception: com.atomikos.jdbc.AtomikosSQLException: Failed to grow the connection pool]
    at org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.initializeBean(AbstractAutowireCapableBeanFactory.java:1578)
    at org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.doCreateBean(AbstractAutowireCapableBeanFactory.java:545)
    at org.springframework.beans.factory.support.AbstractAutowireCapableBeanFactory.createBean(AbstractAutowireCapableBeanFactory.java:482)
    at org.springframework.beans.factory.support.AbstractBeanFactory$1.getObject(AbstractBeanFactory.java:305)
    at org.springframework.beans.factory.support.DefaultSingletonBeanRegistry.getSingleton(DefaultSingletonBeanRegistry.java:230)
    at org.springframework.beans.factory.support.AbstractBeanFactory doGetBean(AbstractBeanFactory.java:301)
SEVERE: One or more listeners failed to start. Full details will be found in the appropriate container log file
May 11, 2016 10:12:43 AM org.apache.catalina.util.SessionIdGeneratorBase createSecureRandom
INFO: Creation of SecureRandom instance for session ID generation using [SHA1PRNG] took [13,256] milliseconds.
May 11, 2016 10:12:43 AM org.apache.catalina.core.StandardContext startInternal
SEVERE: Context [/domibus] startup failed due to previous errors
May 11, 2016 10:12:43 AM org.apache.catalina.core.ApplicationContext log
INFO: Closing Spring root WebApplicationContext
May 11, 2016 10:12:43 AM org.apache.catalina.core.ApplicationContext log
INFO: Shutting down log4j
```

Solution: Setup the password properly in the **domibus.properties**.

20.2. Exception sending context initialized event to listener instance of class

```
SEVERE: Exception sending context initialized event to listener instance of class org.springframework.web.context.ContextLoaderListener
org.springframework.beans.factory.BeanCreationException: Error creating bean with name 'entityManagerFactory' defined in URL
[file:///home/edelivery/domibusf1/conf/domibus/domibus-datasources.xml]: Cannot resolve reference to bean 'domibusJDBC-XADatasource' while setting bean property
'dataSource'; nested exception is org.springframework.beans.factory.BeanCreationException: Error creating bean with name 'domibusJDBC-XADatasource' defined in URL
[file:///home/edelivery/domibusf1/conf/domibus/domibus-datasources.xml]: Invocation of init method failed; nested exception is com.atomikos.jdbc.AtomikosSQLException:
The class 'com.mysql.jdbc.jdbc2.optional.MysqlXADataSource' specified by property 'xaDataSourceClassName' could not be found in the classpath. Please make sure the
spelling is correct, and that the required jar(s) are in the classpath.
```

Solution: Add MySQL connector in *domibus/lib* folder.

20.3. Neither the JAVA_HOME nor the JRE_HOME environment variable is defined

```
Neither the JAVA_HOME nor the JRE_HOME environment variable is defined
At least one of these environment variables is needed to run this program
```

Solution: Set JAVA_HOME variable or/and JRE_HOME.

20.4. Cannot access Admin Console

```
http://your\_server:your\_port\_number/domibus
No SEVER errors in logs but no admin option in browser under
```

Solution: Check if the firewall is open for port_no (e.g. 8080).

20.5. Handshake Failure

Full stack trace below:

```
org.apache.cxf.interceptor.Fault: Could not write attachments.
at org.apache.cxf.interceptor.AttachmentOutInterceptor.handleMessage(AttachmentOutInterceptor.java:74)
at org.apache.cxf.phase.PhaseInterceptorChain.doIntercept(PhaseInterceptorChain.java:308)
at org.apache.cxf.endpoint.ClientImpl.doInvoke(ClientImpl.java:514)
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:423)
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:324)
at org.apache.cxf.endpoint.ClientImpl.invoke(ClientImpl.java:277)
at org.apache.cxf.endpoint.ClientImpl.invokeWrapped(ClientImpl.java:312)
at org.apache.cxf.jaxws.DispatchImpl.invoke(DispatchImpl.java:327)
at org.apache.cxf.jaxws.DispatchImpl.invoke(DispatchImpl.java:246)
at eu.domibus.ebms3.sender.MSHDispatcher.dispatch(MSHDispatcher.java:126)
at eu.domibus.ebms3.sender.MSHDispatcher$$FastClassBySpringCGLIB$$105974a1.invoke(<generated>)
at org.springframework.cglib.proxy.MethodProxy.invoke(MethodProxy.java:204)
at org.springframework.aop.framework.CglibAopProxy$CglibMethodInvocation.invokeJoinpoint(CglibAopProxy.java:717)
at org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:157)
at org.springframework.transaction.interceptor.TransactionInterceptor$1.proceedWithInvocation(TransactionInterceptor.java:99)
at org.springframework.transaction.interceptor.TransactionAspectSupport.invokeWithinTransaction(TransactionAspectSupport.java:281)
at org.springframework.transaction.interceptor.TransactionInterceptor.invoke(TransactionInterceptor.java:96)
at org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:179)
at org.springframework.aop.framework.CglibAopProxy$DynamicAdvisedInterceptor.intercept(CglibAopProxy.java:653)
at eu.domibus.ebms3.sender.MSHDispatcher$$EnhancerBySpringCGLIB$$da53e95a.dispatch(<generated>)
at eu.domibus.ebms3.sender.MessageSender.sendUserMessage(MessageSender.java:116)
at eu.domibus.ebms3.sender.MessageSender.onMessage(MessageSender.java:195)
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:57)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:606)
at org.springframework.aop.support.AopUtils.invokeJoinpointUsingReflection(AopUtils.java:302)
at org.springframework.aop.framework.ReflectiveMethodInvocation.invokeJoinpoint(ReflectiveMethodInvocation.java:190)
at org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:157)
at org.springframework.transaction.interceptor.TransactionInterceptor$1.proceedWithInvocation(TransactionInterceptor.java:99)
at org.springframework.transaction.interceptor.TransactionAspectSupport.invokeWithinTransaction(TransactionAspectSupport.java:281)
```

```
at org.springframework.transaction.interceptor.TransactionInterceptor.invoke(TransactionInterceptor.java:96)
at org.springframework.aop.framework.ReflectiveMethodInvocation.proceed(ReflectiveMethodInvocation.java:179)
at org.springframework.aop.framework.JdkDynamicAopProxy.invoke(JdkDynamicAopProxy.java:207)
at com.sun.proxy.$Proxy163.onMessage(Unknown Source)
at org.springframework.jms.listener.AbstractMessageListenerContainer.doInvokeListener(AbstractMessageListenerContainer.java:746)
at org.springframework.jms.listener.AbstractMessageListenerContainer.invokeListener(AbstractMessageListenerContainer.java:684)
at org.springframework.jms.listener.AbstractMessageListenerContainer.doExecuteListener(AbstractMessageListenerContainer.java:651)
at org.springframework.jms.listener.AbstractPollingMessageListenerContainer.doReceiveAndExecute(AbstractPollingMessageListenerContainer.java:315)
at org.springframework.jms.listener.AbstractPollingMessageListenerContainer.receiveAndExecute(AbstractPollingMessageListenerContainer.java:233)
at org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.invokeListener(DefaultMessageListenerContainer.java:1150)
at org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.executeOngoingLoop(DefaultMessageListenerContainer.java:1142)
at org.springframework.jms.listener.DefaultMessageListenerContainer$AsyncMessageListenerInvoker.run(DefaultMessageListenerContainer.java:1039)
at java.lang.Thread.run(Thread.java:745)
Caused by: javax.net.ssl.SSLHandshakeException: Received fatal alert: handshake_failure
at sun.security.ssl Alerts.getSSLEException(Alerts.java:192)
at sun.security.ssl Alerts.getSSLEException(Alerts.java:154)
at sun.security.ssl SSLSocketImpl.recvAlert(SSLSocketImpl.java:1979)
at sun.security.ssl SSLSocketImpl.readRecord(SSLSocketImpl.java:1086)
at sun.security.ssl SSLSocketImpl.performInitialHandshake(SSLSocketImpl.java:1332)
at sun.security.ssl SSLSocketImpl.startHandshake(SSLSocketImpl.java:1359)
at sun.security.ssl SSLSocketImpl.startHandshake(SSLSocketImpl.java:1343)
at sun.net.www.protocol.https.HttpsClient.afterConnect(HttpsClient.java:563)
at sun.net.www.protocol.https.AbstractDelegateHttpsURLConnection.connect(AbstractDelegateHttpsURLConnection.java:185)
at sun.net.www.protocol.http.HttpURLConnection.getOutputStream(HttpURLConnection.java:1092)
at sun.net.www.protocol.https.HttpsURLConnectionImpl.getOutputStream(HttpsURLConnectionImpl.java:250)
at org.apache.cxf.transport.http.URLConnectionHTTPConduit$URLConnectionWrappedOutputStream.setupWrappedStream(URLConnectionHTTPConduit.java:236)
at org.apache.cxf.transport.http.HTTPConduit$WrappedOutputStream.handleHeadersTrustCaching(HTTPConduit.java:1302)
at org.apache.cxf.transport.http.HTTPConduit$WrappedOutputStream.onFirstWrite(HTTPConduit.java:1262)
at org.apache.cxf.transport.http.URLConnectionHTTPConduit$URLConnectionWrappedOutputStream.onFirstWrite(URLConnectionHTTPConduit.java:267)
at org.apache.cxf.io.AbstractWrappedOutputStream.write(AbstractWrappedOutputStream.java:47)
at org.apache.cxf.io.AbstractThresholdOutputStream.write(AbstractThresholdOutputStream.java:69)
at org.apache.cxf.io.AbstractWrappedOutputStream.write(AbstractWrappedOutputStream.java:60)
at org.apache.cxf.io.CacheAndWriteOutputStream.write(CacheAndWriteOutputStream.java:89)
at org.apache.cxf.attachment.AttachmentSerializer.writeProlog(AttachmentSerializer.java:172)
at org.apache.cxf.interceptor.AttachmentOutInterceptor.handleMessage(AttachmentOutInterceptor.java:72)
... 43 more
```

Solution: If you receive this error, then it's likely that you configured the client with TLSv1.1 while the server only accepts TLSv1.2.

21. ANNEX 1 - USAGE OF CERTIFICATES IN PEPPOL AND OASIS

| | | C2 | | C3 |
|--------|--------------|-------------------------------------------|---------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------|
| | | Keystore | Truststore | Keystore |
| PEPPOL | Certificate: | Sender's (issued by CA) | Empty | Receiver's |
| OASIS | Note: | C2 signs the message with its private key | C2 discover C3's public certificate from the SMP | C3 signs the receipt with its private key |
| | Certificate: | Sender's (issued by CA) | SMP's | Receiver's |
| | Note: | C2 signs the message with its private key | C2 discover C3's public certificate from the SMP To trust the SMP, the sender needs its public certificate | C3 signs the receipt with its private key |
| | | | | Truststore |
| | | | | CA's |
| | | | | The receiver trusts all senders who's certificate were issue dby these CA's |
| | | | | CA's |
| | | | | The receiver trusts all senders who's certificate were issue dby these CA's |

22. ANNEX 2 – DOCUMENT PARTS

23. LIST OF FIGURES

| | |
|------------------------------------------------------------------------------------------|----|
| Figure 1 - Diagram representing the Deployment of Domibus in a Cluster on WebLogic | 23 |
| Figure 2 - Diagram representing the Deployment of Domibus in a Cluster on Tomcat..... | 39 |
| Figure 3 - Diagram representing the Deployment of Domibus in a Cluster on WildFly | 52 |
| Figure 4 - Message Service Handler diagram | 55 |
| Figure 5 - PMode view..... | 68 |

| | |
|-------------------------------------------------------------|-----|
| List of Tables | |
| Table 1 - Domibus Properties | 63 |
| Table 2 - Domibus PMode configuration to ebMS3 mapping..... | 77 |
| Table 3 - Queue Monitoring | 96 |
| Table 4 - SMP Entry Mapping | 122 |

24. CONTACT INFORMATION

CEF Support Team

By email: CEF-EDELIVERY-SUPPORT@ec.europa.eu

By phone: +32 2 299 09 09

- Standard Service: 8am to 6pm (Normal EC working Days)
- Standby Service*: 6pm to 8am (Commission and Public Holidays, Weekends)

* Only for critical and urgent incidents and only by phone